

Royale API Documentation

Version 4.10.0.162

API Documentation



Technical information subject to change without notice. This document may also be changed without notice. 4.10.0.162

Created: August 12, 2021 ©pmdtechnologies ag

All texts, pictures and other contents published in this instruction manual are subject to the copyright of **pmd**, Siegen unless otherwise noticed. No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopy, recording, or any information storage and retrieval system, without permission in writing from the publisher **pmd**.



pmdtechnologies agMartinshardt 1957074 Siegen | Germany

phone +49 271 238712-800 fax +49 271 238712-809 info@pmdtec.com www.pmdtec.com

Page: 2 of 173

API Documentation



Chapter 1

Introduction

The **Royale** software package provides a light-weight camera framework for time-of-flight (ToF) cameras. While being tailored to PMD cameras, the framework enables partners and customers to evaluate and/or integrate 3D TOF technology on/in their target platform. This reduces time to first demo and time to market.

Royale contains all the logic which is required to operate a ToF based camera. The user need not care about setting registers, but can conveniently control the camera via a high-level interface. The Royale framework is completely designed in C++ using the C++11 standard.

1.1 Operating Systems

Royale supports the following operating systems:

- Windows 10
- Linux (tested on Ubuntu 18.04)
- OS X (tested on El Capitan 10.11)
- Android (tested on Android 8)
- Linux ARM (32Bit version tested on Raspbian GNU/Linux 10 (Buster) Raspberry Pi reference 2020-08-20 64Bit version tested on the Odroid C2 with Ubuntu Mate 16.04 ARM 64)

1.2 Hardware Requirements

Royale is tested on the following hardware configurations:

- PC, Intel i7-3770, 3.4 GHz, 4 cores (64 bit)
- MacBook Pro, Intel Core i5, 2.9 Ghz (64 bit)
- · Samsung Galaxy S9

Page: 3 of 173

API Documentation



1.3 Getting Started

For a detailed guide on how to get started with Royale and your camera please have a look at the corresponding Getting Started Guide that can be found in the top folder of the package you received.

1.4 SDK and Examples

Besides the royaleviewer application, the package also provides a Royale SDK which can be used to develop applications using the PMD camera.

There are multiple samples included in the delivery package which should give you a brief overview about the exposed API. You can find an overview in samples/README_samples.md. The *doc* directory offers a detailed description of the Royale API which is a good starting point as well. You can also find the API documentation by opening the API_Documentation.html in the topmost folder of your platform package.

1.4.1 Debugging in Microsoft Visual Studio

To help debugging royale::Vector, royale::Pair and royale::String we provide a Natvis file for Visual Studio. Please take a look at the natvis.md file in the doc/natvis folder of your installation.

1.5 Matlab

In the delivery package for Windows you will find a Matlab wrapper for the Royale library. After the installation it can be found in the matlab subfolder of your installation directory. To use the wrapper you have to include this folder into your Matlab search paths. We also included some examples to show the usage of the wrapper. They can also be found in the matlab folder of your installation.

1.6 Python

In the package you will also find a wrapper to use Royale with Python. Unfortunately this wrapper will only work with specific Python versions. Please have a look at the README.md file in the Python folder to find out which versions are currently supported. In case you want to use a different Python version you can still use the SWIG interface file from the SWIG folder to compile your own wrapper.

1.7 Reference

FAQ: https://pmdtec.com/picofamily/faq/

1.8 License

See ThirdPartySoftware.txt and royale_license.txt. The source code of the open source software used in the Royale binary installation is available at https://oss.pmdtec.com/.

Page: 4 of 173

API Documentation



Chapter 2

Module Index

2.1 Modules

Here is a list of all modules:

Royale	 	

Page: 5 of 173

API Documentation



Page: 6 of 173

API Documentation



Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

CameraManager	 29
DepthData	 34
DepthImage	 38
DepthIRImage	 39
DepthPoint	 41
ICameraDevice	 43
IDepthDataListener	 72
IDepthImageListener	 73
IDepthIRImageListener	 74
IEvent	 76
IEventListener	 78
IExposureListener	 79
IExposureListener2	 80
IExtendedData	 81
IExtendedDataListener	 84
IFrameCaptureListener	
IFrameCaptureListener IRecord	 92
·	
IRecord	 85
IRecord	 85 86
IRecord	 85 86 89
IRecord IIRImageListener IntermediateData IntermediatePoint	 85 86 89 91
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType	 85 86 89 91
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener	 85 86 89 91 91
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener	 85 86 89 91 91 95 97
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener IReplay	 85 86 89 91 91 95 97
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener IReplay IRImage	 85 86 89 91 91 95 97 102
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener IReplay IRImage ISparsePointCloudListener	85 86 89 91 91 95 97 102 103 105
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener IReplay IRImage ISparsePointCloudListener LensParameters	85 86 89 91 91 95 97 102 103 105
IRecord IIRImageListener IntermediateData IntermediatePoint Variant::InvalidType IPlaybackStopListener IRecordStopListener IReplay IRImage ISparsePointCloudListener LensParameters RawData	85 86 89 91 91 95 97 102 103 105 106 110

Page: 7 of 173

API Documentation



Page: 8 of 173

API Documentation



Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

CameraManager	
The CameraManager is responsible for detecting and creating instances of ICameraDevices one for each connected (supported) camera device	29
DepthData	
This structure defines the depth data which is delivered through the callback	34
DepthImage	
The depth image represents the depth and confidence for every pixel	38
DepthIRImage	
This represents combination of both depth and IR image	39
DepthPoint	
Encapsulates a 3D point in object space, with coordinates in meters	41
ICamera Device	
This is the main interface for talking to the time-of-flight camera system	43
IDepthDataListener	
Provides the listener interface for consuming depth data from Royale	72
IDepthImageListener	
Provides a listener interface for consuming depth images from Royale	73
IDepthIRImageListener	
Provides a combined listener interface for consuming both depth and IR images from Royale	74
IEvent	
Interface for anything to be passed via IEventListener	76
IEventListener	
This interface allows observers to receive events	78
IExposureListener	
Provides the listener interface for handling auto-exposure updates in royale	79
IExposureListener2	
Provides the listener interface for handling auto-exposure updates in royale	80

Page: 9 of 173

API Documentation



IExtendedData	
Interface for getting additional data to the standard depth	n data
IExtendedDataListener	
IIRImageListener	
Provides the listener interface for consuming infrared im-	ages from Royale
IntermediateData	
This structure defines the Intermediate depth data which access level 2 for the CameraDevice	th is delivered through the callback if the user has
IntermediatePoint	
	point also stores information which is calculated as
Variant::InvalidType	
IPlaybackStopListener	
Record	
RecordStopListener	sta to got notified when recording stepped offer the
This interface needs to be implemented if the client war	
IReplay	
IRImage	
, ,	l
ISparsePointCloudListener	
	nt clouds from Royale
LensParameters	
•	era module
RawData	
	rough the callback only exposed for access LEVEL 2 106
SparsePointCloud	
	ery valid point
Variant	
Implements a variant type which can take different basic	21
Set to zero	

Page: 10 of 173

API Documentation



Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

Page: 11 of 173

API Documentation



ensParameters.hpp
rocessingFlag.hpp
awData.hpp
parsePointCloud.hpp
pectreProcessingType.hpp
tatus.hpp
treamld.hpp
riggerMode.hpp
ariant.hpp

Page: 12 of 173



Chapter 6

Module Documentation

6.1 Royale

Namespaces

• royale

6.1.1 Detailed Description

Page: 13 of 173

API Documentation



Page: 14 of 173

API Documentation



Chapter 7

Namespace Documentation

7.1 royale Namespace Reference

Namespaces

• parameter

Classes

· class CameraManager

The CameraManager is responsible for detecting and creating instances of ICameraDevices one for each connected (supported) camera device.

struct DepthData

This structure defines the depth data which is delivered through the callback.

• struct DepthImage

The depth image represents the depth and confidence for every pixel.

struct DepthIRImage

This represents combination of both depth and IR image.

• struct DepthPoint

Encapsulates a 3D point in object space, with coordinates in meters.

class ICameraDevice

This is the main interface for talking to the time-of-flight camera system.

· class IDepthDataListener

Provides the listener interface for consuming depth data from Royale.

· class IDepthImageListener

Provides a listener interface for consuming depth images from Royale.

· class IDepthIRImageListener

Provides a combined listener interface for consuming both depth and IR images from Royale.

· class IEvent

Page: 15 of 173

API Documentation



Interface for anything to be passed via IEventListener.

· class IEventListener

This interface allows observers to receive events.

· class IExposureListener

Provides the listener interface for handling auto-exposure updates in royale.

· class IExposureListener2

Provides the listener interface for handling auto-exposure updates in royale.

· class IExtendedData

Interface for getting additional data to the standard depth data.

- · class IExtendedDataListener
- · class IIRImageListener

Provides the listener interface for consuming infrared images from Royale.

• struct IntermediateData

This structure defines the Intermediate depth data which is delivered through the callback if the user has access level 2 for the CameraDevice.

· struct IntermediatePoint

In addition to the standard depth point, the intermediate point also stores information which is calculated as temporaries in the processing pipeline.

- · class IPlaybackStopListener
- · class IRecord
- · class IRecordStopListener

This interface needs to be implemented if the client wants to get notified when recording stopped after the specified number of frames.

- class IReplay
- struct IRImage

Infrared image with 8Bit mono information for every pixel.

• class ISparsePointCloudListener

Provides the listener interface for consuming sparse point clouds from Royale.

· struct LensParameters

This container stores the lens parameters from the camera module.

struct RawData

This structure defines the raw data which is delivered through the callback only exposed for access LEVEL 2.

struct SparsePointCloud

The sparse point cloud gives XYZ and confidence for every valid point.

· class Variant

Implements a variant type which can take different basic data types, the default type is int and the value is set to zero.

Typedefs

• typedef royale::Vector< royale::Pair< royale::ProcessingFlag, royale::Variant >> ProcessingParameterVector

This is a map combining a set of flags which can be set/altered in access LEVEL 2 and the set value as Variant type.

- typedef std::map< royale::ProcessingFlag, royale::Variant > ProcessingParameterMap
- typedef std::pair< royale::ProcessingFlag, royale::Variant > ProcessingParameterPair
- using StreamId = uint16_t

The Streamld uniquely identifies a stream of measurements within a usecase.

Page: 16 of 173

API Documentation



Enumerations

```
• enum TriggerMode { MASTER = 0, SLAVE = 1 }
     Trigger mode used by the camera.

    enum CallbackData: uint16_t { None = 0x00, Raw = 0x01, Depth = 0x02, Intermediate = 0x04 }

     Specifies the type of data which should be captured and returned as callback.

    enum CameraAccessLevel { L1 = 1, L2 = 2, L3 = 3, L4 = 4 }

     This enum defines the access level.

    enum ExposureMode { MANUAL, AUTOMATIC }

     The ExposureMode is used to switch between manual and automatic exposure time handling.
enum FilterLevel {
  Off = 0, Deprecated1 = 1, Deprecated2 = 2, Deprecated3 = 3,
  Deprecated4 = 4, IR1 = 5, IR2 = 6, AF1 = 7,
  CM1 = 8, Binning_1_Basic = 9, Binning_2_Basic = 10, Binning_3_Basic = 11,
  Binning_4_Basic = 12, Binning_8_Basic = 13, Binning_10_Basic = 14, Binning_1_Efficiency = 15,
  Binning_2_Efficiency = 16, Binning_3_Efficiency = 17, Binning_4_Efficiency = 18, Binning_8_Efficiency = 19,
  Binning 10 Efficiency = 20, Legacy = 200, Full = 255, Custom = 256 }
     Royale allows to set different filter levels.
• enum EventSeverity { ROYALE_INFO = 0, ROYALE_WARNING = 1, ROYALE_ERROR = 2, ROYALE_FATAL = 3 }
     Severity of an IEvent.
enum EventType {
  ROYALE CAPTURE STREAM, ROYALE DEVICE DISCONNECTED, ROYALE OVER TEMPERATURE, ROYALE RAW FRAME STA-
  ROYALE EYE SAFETY, ROYALE PROCESSING, ROYALE RECORDING, ROYALE FRAME DROP,
  ROYALE_UNKNOWN, ROYALE_ERROR_DESCRIPTION }
     Type of an IEvent.

    enum ProcessingFlag {

  ConsistencyTolerance Float = 0, FlyingPixelsF0_Float, FlyingPixelsF1_Float, FlyingPixelsFarDist_Float,
  FlyingPixelsNearDist Float, LowerSaturationThreshold Int, UpperSaturationThreshold Int, MPIAmpThreshold Float,
  MPIDistThreshold Float, MPINoiseDistance Float, NoiseThreshold Float, AdaptiveNoiseFilterType Int,
  AutoExposureRefAmplitude_Float, UseAdaptiveNoiseFilter_Bool, UseAutoExposure_Bool, UseRemoveFlyingPixel_Bool,
  UseMPIFlagAverage_Bool, UseMPIFlag_Amp_Bool, UseMPIFlag_Dist_Bool, UseValidateImage_Bool,
  UseRemoveStrayLight_Bool, UseSparsePointCloud_Bool, UseFilter2Freq_Bool, GlobalBinning_Int,
  UseAdaptiveBinning_Bool, AutoExposureRefValue_Float, UseSmoothingFilter_Bool, SmoothingAlpha_Float,
  SmoothingFilterType_Int, UseFlagSBI_Bool, UseHoleFilling_Bool, Reserved1,
  Reserved2, Reserved3, Reserved4, Reserved5,
  Reserved6, Reserved7, Reserved8, AutoExpoMin_Int,
  AutoExpoMax_Int, SpectreProcessingType_Int, UseGrayImageFallbackAmplitude_Bool, GrayImageMeanMap_Int,
  NoiseFilterSigmaD_Float, NoiseFilterIterations_Int, FlyingPixelAngleLimit_Float, FlyingPixelAmpThreshold_Float,
  FlyingPixelMinNeighbors Int, FlyingPixelMaxNeighbors Int, FlyingPixelNoiseRatioThresh Float, SmoothingFilterResetThreshold Float,
  CCThresh Int, PhaseNoiseThresh Float, StraylightThreshold Float, NoiseFilterSigmaA Float,
  TwoFreqCombinationType_Int, UseCorrectMPI_Bool, NUM_FLAGS }
     This is a list of flags which can be set/altered in access LEVEL 2 in order to control the processing pipeline.

    enum SpectreProcessingType {

  AUTO = 1, CB_BINNED_WS = 2, NG = 3, AF = 4,
  CB_BINNED_NG = 5, GRAY_IMAGE = 6, CM_FI = 7, NUM_TYPES }
     This is a list of pipelines that can be set in Spectre.
enum CameraStatus {
  SUCCESS = 0, RUNTIME_ERROR = 1024, DISCONNECTED = 1026, INVALID_VALUE = 1027,
  TIMEOUT = 1028, LOGIC_ERROR = 2048, NOT_IMPLEMENTED = 2049, OUT_OF_BOUNDS = 2050,
  RESOURCE_ERROR = 4096, FILE_NOT_FOUND = 4097, COULD_NOT_OPEN = 4098, DATA_NOT_FOUND = 4099,
  DEVICE_IS_BUSY = 4100, WRONG_DATA_FORMAT_FOUND = 4101, USECASE_NOT_SUPPORTED = 5001,
```

Page: 17 of 173

API Documentation



FRAMERATE_NOT_SUPPORTED = 5002,

EXPOSURE_TIME_NOT_SUPPORTED = 5003, DEVICE_NOT_INITIALIZED = 5004, CALIBRATION_DATA_ERROR

= 5005, INSUFFICIENT_PRIVILEGES = 5006,

DEVICE_ALREADY_INITIALIZED = 5007, EXPOSURE_MODE_INVALID = 5008, NO_CALIBRATION_DATA = 5009,
INSUFFICIENT_BANDWIDTH = 5010,

DUTYCYCLE_NOT_SUPPORTED = 5011, SPECTRE_NOT_INITIALIZED = 5012, NO_USE_CASES = 5013,
NO_USE_CASES_FOR_LEVEL = 5014,
FSM_INVALID_TRANSITION = 8096, UNKNOWN = 0x7fffff01 }

• enum VariantType { Int, Float, Bool, Enum }

Functions

- ROYALE API royale::String getFilterLevelName (royale::FilterLevel level)
- ROYALE_API royale::FilterLevel getFilterLevelFromName (royale::String name)
- ROYALE_API royale::String getProcessingFlagName (royale::ProcessingFlag mode)

For debugging, printable strings corresponding to the ProcessingFlag enumeration.

ROYALE_API bool parseProcessingFlagName (const royale::String &modeName, royale::ProcessingFlag &processing ← Flag)

Convert a string received from getProcessingFlagName back into its ProcessingFlag.

• ROYALE_API ProcessingParameterMap combineProcessingMaps (const ProcessingParameterMap &a, const ProcessingParameterMap &b)

Takes ProcessingParameterMaps a and b and returns a combination of both.

ROYALE_API royale::String getSpectreProcessingTypeName (royale::SpectreProcessingType mode)

Converts the given processing type into a readable string.

ROYALE_API bool getSpectreProcessingTypeFromName (const royale::String &modeName, royale::SpectreProcessingType &processingType)

Converts the name of a processing type into an enum value.

• ROYALE_API royale::String getStatusString (royale::CameraStatus status)

Get a human-readable description for a given error message.

• inline ::std::ostream & operator<< (::std::ostream &os, royale::CameraStatus status)

7.1.1 Typedef Documentation

7.1.1.1 ProcessingParameterMap

typedef std::map< royale::ProcessingFlag, royale::Variant > ProcessingParameterMap

7.1.1.2 ProcessingParameterPair

typedef std::pair< royale::ProcessingFlag, royale::Variant > ProcessingParameterPair

Page: 18 of 173

API Documentation



7.1.1.3 ProcessingParameterVector

typedef royale::Vector< royale::Pair<royale::ProcessingFlag, royale::Variant> > ProcessingParameterVector

This is a map combining a set of flags which can be set/altered in access LEVEL 2 and the set value as Variant type.

The proposed minimum and maximum limits are recommendations for reasonable results. Values beyond these boundaries are permitted, but are currently neither evaluated nor verified.

7.1.1.4 Streamld

```
using StreamId = uint16_t
```

The StreamId uniquely identifies a stream of measurements within a usecase.

A stream is a sequence of periodic measurements having the same depth range, exposure times and other settings. Most usecases will only produce a single stream, but with mixed-mode usecases, there may be more than one. A typical mixed-mode usecase may for example include one stream designed for hand tracking (which needs a high frame rate but can work with reduced depth range) and another one for environment scanning (full depth range at a lower frame rate).

Streamld 0 is not a valid Streamld, but can (for backward compatibility) be used as referring to the single stream contained in non mixed mode usecases in most API functions that expect a Streamld. This allows applications that don't make use of mixed mode to work without having to deal with Streamlds. Applications that need to use mixed mode usecases will have to provide the correct IDs in the API as 0 is not accepted as Streamld if a mixed mode usecase is active.

7.1.2 Enumeration Type Documentation

7.1.2.1 CallbackData

```
enum CallbackData : uint16_t [strong]
```

Specifies the type of data which should be captured and returned as callback.

Enumerator

None	only get the callback but no data delivery
Raw	raw frames, if exclusively used no processing pipe is executed (no calibration data is needed)
Depth	one depth and grayscale image will be delivered for the complete sequence
Intermediate	all intermediate data will be delivered which are generated in the processing pipeline

Page: 19 of 173

API Documentation



7.1.2.2 CameraAccessLevel

enum CameraAccessLevel [strong]

This enum defines the access level.

For Royale \geq 3.5 this can be directly cast to unsigned ints (Level 1 equals 1, Level 2 equals 2, ...).

Enumerator

L1	Level 1 access provides depth data using standard, known-working configurations.
L2	Level 2 access provides raw data, e.g. for custom processing pipelines
L3	Level 3 access enables you to overwrite exposure limits.
L4	Level 4 access is for bringing up new camera modules.

7.1.2.3 CameraStatus

enum CameraStatus [strong]

Enumerator

Indicates that there isn't an error.
Something unexpected happened.
Camera device is disconnected.
The value provided is invalid.
The connection got a timeout.
This does not make any sense here.
This feature is not implemented yet.
Setting/parameter is out of specified range.
Cannot access resource.
Specified file was not found.
Cannot open resource.
No data available where expected.
Another action is in progress.
A resource was expected to be in one data format, but was in a different (recognisable) format.
This use case is not supported.

Page: 20 of 173

API Documentation



Enumerator

FRAMERATE_NOT_SUPPORTED	The specified frame rate is not supported.
EXPOSURE_TIME_NOT_SUPPORTED	The exposure time is not supported.
DEVICE_NOT_INITIALIZED	The device seems to be uninitialized.
CALIBRATION_DATA_ERROR	The calibration data is not readable.
INSUFFICIENT_PRIVILEGES	The camera access level does not allow to call this operation.
DEVICE_ALREADY_INITIALIZED	The camera was already initialized.
EXPOSURE_MODE_INVALID	The current set exposure mode does not support this operation.
NO_CALIBRATION_DATA	The method cannot be called since no calibration data is available.
INSUFFICIENT_BANDWIDTH	The interface to the camera module does not provide a sufficient bandwidth.
DUTYCYCLE_NOT_SUPPORTED	The duty cycle is not supported.
SPECTRE_NOT_INITIALIZED	Spectre was not initialized properly.
NO_USE_CASES	The camera offers no use cases.
NO_USE_CASES_FOR_LEVEL	The camera offers no use cases for the current access level.
FSM_INVALID_TRANSITION	Camera module state machine does not support current transition.
UNKNOWN	Catch-all failure.

7.1.2.4 EventSeverity

enum EventSeverity [strong]

Severity of an IEvent.

Enumerator

ROYALE_INFO	Information only event.	
ROYALE_WARNING	Potential issue detected (e.g. soft overtemperature limit reached).	
ROYALE_ERROR	Errors occurred during operation. The operation (e.g. recording or stream capture) has failed and was stopped.	
ROYALE_FATAL	A severe error was detected. The corresponding ICameraDevice is no longer in a usable state.	

7.1.2.5 EventType

enum EventType [strong]

Type of an IEvent.

Page: 21 of 173

API Documentation



Enumerator

ROYALE_CAPTURE_STREAM	The event was detected as part of the mechanism to receive image data. For events of this class, ROYALE_WARNING is likely to indicate dropped frames, and ROYALE_ERROR is likely to indicate that no more frames will be captured until after the next call to ICameraDevice::startCapture().
ROYALE_DEVICE_DISCONNECTED	Royale is no longer able to talk to the camera; this is always severity ROYALE_FATAL.
ROYALE_OVER_TEMPERATURE	The camera has become hot, likely because of the illumination. For events of this class, ROYALE_WARNING indicates that the device is still functioning but is near to the temperature at which it will be shut down for safety, and ROYALE_ERROR indicates that the safety mechanism has been triggered.
ROYALE_RAW_FRAME_STATS	This event is sent regularly during capturing. The trigger for sending this event is implementation defined and varies for different use cases, but the timing is normally around one per second. If all frames were successfully received then it will be ROYALE_INFO, if any were dropped then it will be ROYALE_WARNING.
ROYALE_EYE_SAFETY	This event indicates that the camera's internal monitor of the power used by the illumination has been triggered, which is never expected to happen with the use cases in production devices. The capturing should already been stopped when receiving this event, as the illumination will stay turned off and most of the received data will be corrupted. This is always severity ROYALE_FATAL.
ROYALE_PROCESSING	This event is sent if, for example, the backend of the processing is changed.
ROYALE_RECORDING	This event is sent if something happens during the recording.
ROYALE_FRAME_DROP	This event is sent when a frame drop occurs.
ROYALE_UNKNOWN	The event type is for any event for which there is no official API specification.
ROYALE_ERROR_DESCRIPTION	This event type can be used to get more information about errors that are returned by Royale.

7.1.2.6 ExposureMode

enum ExposureMode [strong]

The ExposureMode is used to switch between manual and automatic exposure time handling.

Enumerator

MANUAL	Camera exposure mode set to manual.
	Camera exposure mode set to automatic.
AUTOMATIC	

Page: 22 of 173

API Documentation



7.1.2.7 FilterLevel

enum FilterLevel [strong]

Royale allows to set different filter levels.

Internally these represent different configurations of the processing pipeline. Which filter levels are available depends on the currently selected pipeline.

Enumerator

Off	Turn off all filtering of the data (validation will still be enabled) (WS pipeline)
Deprecated1	Not available anymore.
Deprecated2	Not available anymore.
Deprecated3	Not available anymore.
Deprecated4	Not available anymore.
IR1	Only available for the IR/FaceID pipeline : IR_IlluOn-FPN.
IR2	Only available for the IR/FaceID pipeline : IR_IlluOn-IlluOff.
AF1	Standard setting for the auto focus pipeline.
CM1	Standard setting for the coded modulation pipeline.
Binning_1_Basic	NG pipeline : basic kernels with binning size 1.
Binning_2_Basic	NG pipeline : basic kernels with binning size 2.
Binning_3_Basic	NG pipeline : basic kernels with binning size 3.
Binning_4_Basic	NG pipeline : basic kernels with binning size 4.
Binning_8_Basic	NG pipeline : basic kernels with binning size 8.
Binning_10_Basic	NG pipeline : basic kernels with binning size 10.
Binning_1_Efficiency	NG pipeline : efficiency kernels with binning size 1.
Binning_2_Efficiency	NG pipeline : efficiency kernels with binning size 2.
Binning_3_Efficiency	NG pipeline : efficiency kernels with binning size 3.
Binning_4_Efficiency	NG pipeline : efficiency kernels with binning size 4.
Binning_8_Efficiency	NG pipeline : efficiency kernels with binning size 8.
Binning_10_Efficiency	NG pipeline : efficiency kernels with binning size 10.
Legacy	Standard settings for older cameras (WS pipeline)
Full	Enable all filters that are available for this camera (WS pipeline)
Custom	Value returned by getFilterLevel if the processing parameters differ from all of the presets.

Page: 23 of 173

API Documentation



7.1.2.8 ProcessingFlag

enum ProcessingFlag [strong]

This is a list of flags which can be set/altered in access LEVEL 2 in order to control the processing pipeline.

The suffix type indicates the expected Variant type. For a more detailed description of the different parameters please refer to the documentation you will receive after getting LEVEL 2 access.

Make sure to retrieve and update all the flags when SpectreProcessingType_Int is altered.

Keep in mind, that if this list is changed, the map with names has to be adapted!

Enumerator

ConsistencyTolerance_Float	Consistency limit for asymmetry validation.
FlyingPixelsF0_Float	Scaling factor for lower depth value normalization.
FlyingPixelsF1_Float	Scaling factor for upper depth value normalization.
FlyingPixelsFarDist_Float	Upper normalized threshold value for flying pixel detection.
FlyingPixelsNearDist_Float	Lower normalized threshold value for flying pixel detection.
LowerSaturationThreshold_Int	Lower limit for valid raw data values.
UpperSaturationThreshold_Int	Upper limit for valid raw data values.
MPIAmpThreshold_Float	Threshold for MPI flags triggered by amplitude discrepancy.
MPIDistThreshold_Float	Threshold for MPI flags triggered by distance discrepancy.
MPINoiseDistance_Float	Threshold for MPI flags triggered by noise.
NoiseThreshold_Float	Upper threshold for final distance noise.
AdaptiveNoiseFilterType_Int	Kernel type of the adaptive noise filter.
AutoExposureRefAmplitude_Float	DEPRECATED : The reference amplitude for the new exposure estimate.
UseAdaptiveNoiseFilter_Bool	Activate spatial filter reducing the distance noise.
UseAutoExposure_Bool	DEPRECATED : Activate dynamic control of the exposure time.
UseRemoveFlyingPixel_Bool	Activate FlyingPixel flag.
UseMPIFlagAverage_Bool	Activate spatial averaging MPI value before thresholding.
UseMPIFlag_Amp_Bool	Activates MPI-amplitude flag.
UseMPIFlag_Dist_Bool	Activates MPI-distance flag.
UseValidateImage_Bool	Activates output image validation.
UseRemoveStrayLight_Bool	Activates the removal of stray light.
UseSparsePointCloud_Bool	DEPRECATED : Creates a sparse-point cloud in Spectre.
UseFilter2Freq_Bool	Activates 2 frequency filtering.
GlobalBinning_Int	Sets the size of the global binning kernel.
UseAdaptiveBinning_Bool	DEPRECATED : Activates adaptive binning.
AutoExposureRefValue_Float	The reference value for the new exposure estimate.
UseSmoothingFilter_Bool	Enable/Disable the smoothing filter.
SmoothingAlpha_Float	The alpha value used for the smoothing filter.
SmoothingFilterType_Int	Determines the type of smoothing that is used.

Page: 24 of 173

API Documentation



Enumerator

UseFlagSBI_Bool	Enable/Disable the flagging of pixels where the SBI was active.
UseHoleFilling Bool	Enable/Disable the hole filling algorithm.
Reserved1	
Reserved2	
Reserved3	
Reserved4	
Reserved5	
Reserved6	
Reserved7	
Reserved8	
AutoExpoMin_Int	The minimum value for the auto exposure algorithm (new values will be bound by use case limits)
AutoExpoMax_Int	The maximum value for the auto exposure algorithm (new values will be bound by use case limits)
SpectreProcessingType_Int	The type of processing used by Spectre.
UseGrayImageFallbackAmplitude_Bool	Uses the fallback image in the gray image pipeline as amplitude image.
GrayImageMeanMap_Int	Value where the mean of the gray image is mapped to.
NoiseFilterSigmaD_Float	SigmaD.
NoiseFilterIterations_Int	Iterations of the noise filter.
FlyingPixelAngleLimit_Float	Angle limit of the flying pixel algorithm.
FlyingPixelAmpThreshold_Float	Amplitude threshold of the flying pixel algorithm.
FlyingPixelMinNeighbors_Int	Minimum neighbors for the flying pixel algorithm.
FlyingPixelMaxNeighbors_Int	Maximum neighbors for the flying pixel algorithm.
FlyingPixelNoiseRatioThresh_Float	Noiseratio threshold.
SmoothingFilterResetThreshold_Float	Reset value for the smoothing.
CCThresh_Int	Connected components threshold.
PhaseNoiseThresh_Float	PhaseNoise threshold.
StraylightThreshold_Float	Straylight threshold.
NoiseFilterSigmaA_Float	SigmaA.
TwoFreqCombinationType_Int	Determines which algorithm will be used for combining the two frequencies.
UseCorrectMPI_Bool	Turn on/off the MPI correction of the spot processing algorithm.
NUM_FLAGS	

7.1.2.9 SpectreProcessingType

enum SpectreProcessingType [strong]

This is a list of pipelines that can be set in Spectre.

Which pipelines are available depends on the module and the currently selected use case.

Page: 25 of 173

API Documentation



Enumerator

AUTO	
CB_BINNED_WS	
NG	
AF	
CB_BINNED_NG	
GRAY_IMAGE	
CM_FI	
NUM_TYPES	

7.1.2.10 TriggerMode

enum TriggerMode [strong]

Trigger mode used by the camera.

Enumerator

MASTER	The camera acts as a master.
SLAVE	The camera acts as a slave.

7.1.2.11 VariantType

enum VariantType [strong]

Enumerator

Int	
Float	
Bool	
Enum	

7.1.3 Function Documentation

Page: 26 of 173

API Documentation



7.1.3.1 combineProcessingMaps()

Takes ProcessingParameterMaps a and b and returns a combination of both.

Keys that exist in both maps will take the value of map b.

7.1.3.2 getFilterLevelFromName()

7.1.3.3 getFilterLevelName()

7.1.3.4 getProcessingFlagName()

For debugging, printable strings corresponding to the ProcessingFlag enumeration.

The returned value is copy of the processing flag name. If the processing flag is not found an empty string will be returned.

These strings will not be localized.

7.1.3.5 getSpectreProcessingTypeFromName()

Converts the name of a processing type into an enum value.

Page: 27 of 173

API Documentation



7.1.3.6 getSpectreProcessingTypeName()

Converts the given processing type into a readable string.

7.1.3.7 getStatusString()

Get a human-readable description for a given error message.

Note: These descriptions are in English and are intended to help developers, they're not translated to the current locale.

Examples

sampleRecordRRF.cpp.

7.1.3.8 operator << ()

7.1.3.9 parseProcessingFlagName()

Convert a string received from getProcessingFlagName back into its ProcessingFlag.

If the processing flag name is not found the method returns false. Else the method will return true.

7.2 royale::parameter Namespace Reference

Page: 28 of 173

API Documentation



Chapter 8

Class Documentation

8.1 CameraManager Class Reference

The CameraManager is responsible for detecting and creating instances of ICameraDevices one for each connected (supported) camera device.

#include <CameraManager.hpp>

Public Member Functions

ROYALE_API CameraManager (const royale::String &activationCode="")

Constructor of the CameraManager.

• ROYALE_API ~CameraManager ()

Destructor of the CameraManager.

ROYALE_API royale::Vector < royale::String > getConnectedCameraList ()

Returns the list of connected camera modules identified by a unique ID (serial number).

ROYALE_API std::unique_ptr< royale::ICameraDevice > createCamera (const royale::String &camerald, const royale::TriggerMode mode=TriggerMode::MASTER)

Creates a master or slave camera object ICameraDevice identified by its ID.

 $\bullet \ \ \mathsf{ROYALE_API} \ \ \mathsf{royale::} \\ \mathsf{String} > \mathsf{getConnectedCameraNames} \ ()$

This function has to be called after getConnectedCameraList().

• ROYALE_API royale::CameraStatus registerEventListener (royale::IEventListener *listener)

Register an event listener with this camera manager.

ROYALE_API royale::CameraStatus unregisterEventListener ()

Unregister the current event listener of this camera manager.

ROYALE_API void setCacheFolder (const royale::String &path)

Sets the folder that will be used for caching e.g.

Page: 29 of 173

API Documentation



Static Public Member Functions

• static ROYALE_API royale::CameraAccessLevel getAccessLevel (const royale::String &activationCode="")

Retrieves the access level to the given activation code.

8.1.1 Detailed Description

The CameraManager is responsible for detecting and creating instances of ICameraDevices one for each connected (supported) camera device.

Depending on the provided activation code access $\texttt{Level}\ 2$ or $\texttt{Level}\ 3$ can be created. Due to eye safety reasons, $\texttt{Level}\ 3$ is for internal purposes only. Once a known time-of-flight device is detected, the according communication (e.g. via USB) is established and the camera device is ready.

Examples

sampleCameraInfo.cpp, sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, sampleRecordRRF.cpp, and sampleRetrieveData.cpp.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 CameraManager()

 $Constructor\ of\ the\ {\color{blue}Camera Manager}.$

An empty activationCode only allows to get an ICameraDevice. A valid activation code also allows to gain Level 2 or Level 3 access rights.

8.1.2.2 ~CameraManager()

```
ROYALE_API ~CameraManager ( )
```

Destructor of the CameraManager.

8.1.3 Member Function Documentation

Page: 30 of 173

API Documentation



8.1.3.1 createCamera()

Creates a master or slave camera object ICameraDevice identified by its ID.

The ID can be

- The ID which is returned by getConnectedCameraList (representing a physically connected camera)
- · A given filename of a previously recorded stream

If the ID or filename are not correct, a nullptr will be returned. The ownership is transfered to the caller, which means that the ICameraDevice is still valid once the CameraManager is out of scope.

In case of a given filename, the returned ICameraDevice can also be dynamically casted to an IReplay interface which offers more playback functionality.

If the camera is opened as a slave it will not receive a start signal from Royale, but will wait for the external trigger signal. Please have a look at the master/slave example which shows how to deal with multiple cameras.

Parameters

camera← Id	Unique ID either the ID returned from getConnectedCameraList of a filename for a recorded stream
mode	Tell Royale to open this camera as master or slave.

Returns

ICameraDevice object if ID was found, nullptr otherwise

Examples

sampleCameraInfo.cpp, sampleExportPLY.cpp, sampleOpenCV.cpp, sampleRecordRRF.cpp, and sampleRetrieveData.cpp.

8.1.3.2 getAccessLevel()

Retrieves the access level to the given activation code.

Page: 31 of 173

API Documentation



8.1.3.3 getConnectedCameraList()

```
ROYALE_API royale::Vector<royale::String> getConnectedCameraList ( )
```

Returns the list of connected camera modules identified by a unique ID (serial number).

This call tries to connect to each plugged-in camera and queries for its unique serial number. Found cameras need to be fetched by calling createCamera(). This in turn moves the ownership of the CameraDevice to the caller of createCamera(). Calling getConnectedCameraList() twice will automatically close all unused ICameraDevices that were returned from the first call. Calling this function twice is not the expected usage for this function! Once the scope of CameraManager ends, all (other) unused ICameraDevices will also be closed automatically. The createCamera() keeps the ICameraDevice beyond the scope of the CameraManager since the ownership is given to the caller.

WARNING: please also only have one instance of CameraManager at the same time! royale does not support multiple instances of CameraManager in parallel. The caller will receive events through the event listener registered with registerEventListener() under the respective conditions:

Event	Condition
EventImagerConfigNotFound	The external configuration file is not found.
EventProbedDevicesNotMatched	There are connected devices which may be cameras but none of them were found suitable for inclusion in the connected camera list.

Returns

list of connected camera IDs

Examples

 $sample Camera Info.cpp, \ sample Open CV.cpp, \ sample Record RRF.cpp, \ \textbf{and} \ sample Retrieve Data.cpp.$

8.1.3.4 getConnectedCameraNames()

```
ROYALE_API royale::Vector<royale::String> getConnectedCameraNames ( )
```

This function has to be called after getConnectedCameraList().

It returns the list of connected camera names without creating them.

Returns

list of connected camera Names

Page: 32 of 173

API Documentation



8.1.3.5 registerEventListener()

Register an event listener with this camera manager.

The listener may receive an event if an error occurs during a following call to one of the camera manager's other methods. For the conditions under which an error event occurs, see the respective method:

• getConnectedCameraList()

Parameters

listener	the listener to be registered.
----------	--------------------------------

Returns

SUCCESS if the event listener was successfully registered.

See also

unregisterEventListener().

Examples

sampleCameraInfo.cpp.

8.1.3.6 setCacheFolder()

Sets the folder that will be used for caching e.g.

calibration files.

Page: 33 of 173

API Documentation



8.1.3.7 unregisterEventListener()

ROYALE_API royale::CameraStatus unregisterEventListener ()

Unregister the current event listener of this camera manager.

This method blocks until all pending events are sent to the listener. A registered event listener should be unregistered before it is deallocated. The event listener is automatically unregistered when this camera manager is deallocated.

Returns

SUCCESS if the event listener was successfully unregistered.

See also

registerEventListener().

Examples

sampleCameraInfo.cpp.

The documentation for this class was generated from the following file:

CameraManager.hpp

8.2 DepthData Struct Reference

This structure defines the depth data which is delivered through the callback.

#include <DepthData.hpp>

Public Member Functions

• DepthData & operator= (const DepthData &dd)

Page: 34 of 173

API Documentation



Public Attributes

· int version

version number of the data format

• std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

· Streamld streamld

stream which produced the data

• uint16_t width

width of depth image

· uint16_t height

height of depth image

royale::Vector< uint32_t > exposureTimes

exposureTimes retrieved from CapturedUseCase

royale::Vector < royale::DepthPoint > points

array of points

• bool hasDepth

to check presence of depth information

8.2.1 Detailed Description

This structure defines the depth data which is delivered through the callback.

This data comprises a dense 3D point cloud with the size of the depth image (width, height). The points vector encodes an array (row-based) with the size of (width x height). Based on the depthConfidence, the user can decide to use the 3D point or not. The point cloud uses a right handed coordinate system ($x \rightarrow$ right, $y \rightarrow$ down, $z \rightarrow$ in viewing direction).

Although the points are provided as a (width * height) array and are arranged in a grid, treating them as simple square pixels will provide a distorted image, because they are not necessarily in a rectilinear projection; it is more likely that the camera would have a wide-angle or even fish-eye lens. Each individual DepthPoint provides x and y coordinates in addition to the z cooordinate, these values in the individual DepthPoints will match the lens of the camera.

Examples

sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, and sampleRetrieveData.cpp.

8.2.2 Member Function Documentation

8.2.2.1 operator=()

Page: 35 of 173

API Documentation



8.2.3 Member Data Documentation

8.2.3.1 exposureTimes

royale::Vector<uint32_t> exposureTimes

exposureTimes retrieved from CapturedUseCase

Examples

sampleRetrieveData.cpp.

8.2.3.2 hasDepth

bool hasDepth

to check presence of depth information

8.2.3.3 height

uint16_t height

height of depth image

Examples

sampleOpenCV.cpp, and sampleRetrieveData.cpp.

8.2.3.4 points

royale::DepthPoint> points

array of points

Examples

sampleExportPLY.cpp, sampleOpenCV.cpp, and sampleRetrieveData.cpp.

Page: 36 of 173

API Documentation



8.2.3.5 streamld

StreamId streamId

stream which produced the data

Examples

sampleRetrieveData.cpp.

8.2.3.6 timeStamp

std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

Examples

sampleIReplay.cpp.

8.2.3.7 version

int version

version number of the data format

8.2.3.8 width

uint16_t width

width of depth image

Examples

sampleOpenCV.cpp, and sampleRetrieveData.cpp.

The documentation for this struct was generated from the following file:

• DepthData.hpp

Page: 37 of 173

API Documentation



8.3 DepthImage Struct Reference

The depth image represents the depth and confidence for every pixel.

#include <DepthImage.hpp>

Public Attributes

int64_t timestamp

timestamp for the frame

Streamld streamld

stream which produced the data

• uint16_t width

width of depth image

· uint16_t height

height of depth image

royale::Vector< uint16_t > cdData

depth and confidence for the pixel

8.3.1 Detailed Description

The depth image represents the depth and confidence for every pixel.

The least significant 13 bits are the depth (z value along the optical axis) in millimeters. 0 stands for invalid measurement / no data.

The most significant 3 bits correspond to a confidence value. 0 is the highest confidence, 7 the second highest, and 1 the lowest.

note The meaning of the confidence bits changed between Royale v3.14.0 and v3.15.0. Before v3.15.0, zero was lowest and 7 was highest. Because of this, the member was renamed from "data" to "cdData".

8.3.2 Member Data Documentation

8.3.2.1 cdData

royale::Vector<uint16_t> cdData

depth and confidence for the pixel

Page: 38 of 173

API Documentation



8.3.2.2 height

uint16_t height

height of depth image

8.3.2.3 streamld

StreamId streamId

stream which produced the data

8.3.2.4 timestamp

int64_t timestamp

timestamp for the frame

8.3.2.5 width

uint16_t width

width of depth image

The documentation for this struct was generated from the following file:

• DepthImage.hpp

8.4 DepthIRImage Struct Reference

This represents combination of both depth and IR image.

#include <DepthIRImage.hpp>

Page: 39 of 173

API Documentation



Public Attributes

int64_t timestamp

timestamp for the frame

· Streamld streamld

stream which produced the data

• uint16_t width

width of depth image

• uint16_t height

height of depth image

• royale::Vector< uint16_t > dpData

depth and confidence for the pixel

 $\bullet \ \ \mathsf{royale} \\ :: \\ \mathsf{Vector} \\ < \\ \mathsf{uint8_t} \\ > \\ \mathsf{irData} \\$

8Bit mono IR image

8.4.1 Detailed Description

This represents combination of both depth and IR image.

Provides depth, confidence and IR 8Bit mono information for every pixel.

8.4.2 Member Data Documentation

8.4.2.1 dpData

royale::Vector<uint16_t> dpData

depth and confidence for the pixel

8.4.2.2 height

uint16_t height

height of depth image

Page: 40 of 173

API Documentation



8.4.2.3 irData

royale::Vector<uint8_t> irData

8Bit mono IR image

8.4.2.4 streamld

StreamId streamId

stream which produced the data

8.4.2.5 timestamp

int64_t timestamp

timestamp for the frame

8.4.2.6 width

uint16_t width

width of depth image

The documentation for this struct was generated from the following file:

• DepthIRImage.hpp

8.5 DepthPoint Struct Reference

Encapsulates a 3D point in object space, with coordinates in meters.

#include <DepthData.hpp>

Page: 41 of 173

API Documentation



Public Attributes

• float x

X coordinate [meters].

float y

Y coordinate [meters].

float z

Z coordinate [meters].

· float noise

noise value [meters]

• uint16_t grayValue

16-bit gray value

• uint8_t depthConfidence

value from 0 (invalid) to 255 (full confidence)

8.5.1 Detailed Description

Encapsulates a 3D point in object space, with coordinates in meters.

In addition to the X/Y/Z coordinate each point also includes a gray value, a noise standard deviation, and a depth confidence value.

8.5.2 Member Data Documentation

8.5.2.1 depthConfidence

uint8_t depthConfidence

value from 0 (invalid) to 255 (full confidence)

8.5.2.2 grayValue

uint16_t grayValue

16-bit gray value

Page: 42 of 173

API Documentation



8.5.2.3 noise float noise noise value [meters] 8.5.2.4 x float x X coordinate [meters]. 8.5.2.5 y float y Y coordinate [meters]. 8.5.2.6 z float z Z coordinate [meters]. The documentation for this struct was generated from the following file: • DepthData.hpp

8.6 ICameraDevice Class Reference

This is the main interface for talking to the time-of-flight camera system.

#include <ICameraDevice.hpp>

API Documentation



Public Member Functions

- virtual ∼ICameraDevice ()
- virtual royale::CameraStatus initialize ()=0

LEVEL 1 Initializes the camera device and sets the first available use case.

• virtual royale::CameraStatus initialize (const royale::String &initUseCase)=0

LEVEL 1 Initialize the camera and configure the system for the specified use case.

• virtual royale::CameraStatus getId (royale::String &id) const =0

LEVEL 1 Get the ID of the camera device.

• virtual royale::CameraStatus getCameraName (royale::String &cameraName) const =0

LEVEL 1 Returns the associated camera name as a string which is defined in the CoreConfig of each module.

- virtual royale::CameraStatus getCameraInfo (royale::Vector< royale::Pair< royale::String, royale::String >> &camInfo)
 const =0
- virtual royale::CameraStatus setUseCase (const royale::String &name)=0

LEVEL 1 Sets the use case for the camera.

virtual royale::CameraStatus getUseCases (royale::Vector< royale::String > &useCases) const =0

LEVEL 1 Returns all use cases which are supported by the connected module and valid for the current selected CallbackData information (e.g.

- virtual royale::CameraStatus getStreams (royale::Vector < royale::StreamId > &streams) const =0
 - LEVEL 1 Get the streams associated with the current use case.
- virtual royale::CameraStatus getNumberOfStreams (const royale::String &name, uint32_t &nrStreams) const =0

LEVEL 1 Retrieves the number of streams for a specified use case.

• virtual royale::CameraStatus getCurrentUseCase (royale::String &useCase) const =0

LEVEL 1 Gets the current use case as string.

• virtual royale::CameraStatus setExposureTime (uint32_t exposureTime, royale::StreamId streamId=0)=0

LEVEL 1 Change the exposure time for the supported operated operation modes.

• virtual royale::CameraStatus setExposureMode (royale::ExposureMode exposureMode, royale::StreamId=0)=0

LEVEL 1 Change the exposure mode for the supported operated operation modes.

virtual royale::CameraStatus getExposureMode (royale::ExposureMode &exposureMode, royale::StreamId streamId=0)
 const =0

LEVEL 1 Retrieves the current mode of operation for acquisition of the exposure time.

virtual royale::CameraStatus getExposureLimits (royale::Pair< uint32_t, uint32_t > &exposureLimits, royale::StreamId streamId=0) const =0

LEVEL 1 Retrieves the minimum and maximum allowed exposure limits of the specified operation mode.

- virtual royale::CameraStatus registerDataListener (royale::IDepthDataListener *listener)=0
- virtual royale::CameraStatus unregisterDataListener ()=0

LEVEL 1 Unregisters the data depth listener.

- virtual royale::CameraStatus registerDepthImageListener (royale::IDepthImageListener *listener)=0
 - LEVEL 1 Once registering the data listener, Android depth image data is sent via the callback function.
- virtual royale::CameraStatus unregisterDepthImageListener ()=0

LEVEL 1 Unregisters the depth image listener.

- virtual royale::CameraStatus registerSparsePointCloudListener (royale::ISparsePointCloudListener *listener)=0
 - LEVEL 1 Once registering the data listener, Android point cloud data is sent via the callback function.
- virtual royale::CameraStatus unregisterSparsePointCloudListener ()=0

LEVEL 1 Unregisters the sparse point cloud listener.

- virtual royale::CameraStatus registerIRImageListener (royale::IIRImageListener *listener)=0
 - LEVEL 1 Once registering the data listener, IR image data is sent via the callback function.
- virtual royale::CameraStatus unregisterIRImageListener ()=0

LEVEL 1 Unregisters the IR image listener.

• virtual royale::CameraStatus registerDepthIRImageListener (royale::IDepthIRImageListener *listener)=0

Page: 44 of 173

API Documentation



LEVEL 1 Once registering the data listener, depth and IR image data is sent via the callback function.

• virtual royale::CameraStatus unregisterDepthIRImageListener ()=0

LEVEL 1 Unregisters the DepthIR image listener.

• virtual royale::CameraStatus registerEventListener (royale::IEventListener *listener)=0

LEVEL 1 Register listener for event notifications.

virtual royale::CameraStatus unregisterEventListener ()=0

LEVEL 1 Unregisters listener for event notifications.

• virtual royale::CameraStatus startCapture ()=0

LEVEL 1 Starts the video capture mode (free-running), based on the specified operation mode.

virtual royale::CameraStatus stopCapture ()=0

LEVEL 1 Stops the video capturing mode.

virtual royale::CameraStatus getMaxSensorWidth (uint16_t &maxSensorWidth) const =0

LEVEL 1 Returns the maximal width supported by the camera device.

virtual royale::CameraStatus getMaxSensorHeight (uint16_t &maxSensorHeight) const =0

LEVEL 1 Returns the maximal height supported by the camera device.

- virtual royale::CameraStatus getLensParameters (royale::LensParameters ¶m) const =0
- virtual royale::CameraStatus isConnected (bool &connected) const =0

LEVEL 1 Returns the information if a connection to the camera could be established.

• virtual royale::CameraStatus isCalibrated (bool &calibrated) const =0

LEVEL 1 Returns the information if the camera module is calibrated.

• virtual royale::CameraStatus isCapturing (bool &capturing) const =0

LEVEL 1 Returns the information if the camera is currently in capture mode.

• virtual royale::CameraStatus getAccessLevel (royale::CameraAccessLevel &accessLevel) const =0

LEVEL 1 Returns the current camera device access level.

- virtual royale::CameraStatus startRecording (const royale::String &fileName, uint32_t numberOfFrames=0, uint32_
 t frameSkip=0, uint32_t msSkip=0)=0
- virtual royale::CameraStatus stopRecording ()=0

LEVEL 1 Stop recording the raw data stream into a file.

- virtual royale::CameraStatus registerRecordListener (royale::IRecordStopListener *listener)=0
- virtual royale::CameraStatus unregisterRecordListener ()=0

LEVEL 1 Unregisters the record listener.

• virtual royale::CameraStatus registerExposureListener (royale::IExposureListener *listener)=0

LEVEL 1 [deprecated] Once registering the exposure listener, new exposure values calculated by the processing are sent to the listener.

• virtual royale::CameraStatus registerExposureListener (royale::IExposureListener2 *listener)=0

LEVEL 1 Once registering the exposure listener, new exposure values calculated by the processing are sent to the listener.

• virtual royale::CameraStatus unregisterExposureListener ()=0

LEVEL 1 Unregisters the exposure listener.

virtual royale::CameraStatus setFrameRate (uint16_t framerate)=0

LEVEL 1 Set the frame rate to a value.

virtual royale::CameraStatus getFrameRate (uint16_t &frameRate) const =0

LEVEL 1 Get the current frame rate which is set for the current use case.

• virtual royale::CameraStatus getMaxFrameRate (uint16_t &maxFrameRate) const =0

LEVEL 1 Get the maximal frame rate which can be set for the current use case.

• virtual royale::CameraStatus setExternalTrigger (bool useExternalTrigger)=0

LEVEL 1 Enable or disable the external triggering.

virtual royale::CameraStatus setFilterLevel (const royale::FilterLevel level, royale::StreamId streamId=0)=0

LEVEL 1 Change the level of filtering that is used during the processing.

• virtual royale::CameraStatus getFilterLevel (royale::FilterLevel &level, royale::StreamId streamId=0) const =0

Page: 45 of 173

API Documentation



LEVEL 1 Retrieve the level of filtering for the given streamld.

virtual royale::CameraStatus getFilterLevels (royale::Vector < royale::FilterLevel > &levels, royale::StreamId streamId=0)
 const =0

LEVEL 1 Retrieve the levels of filtering that are available for the given streamld.

• virtual royale::CameraStatus getExposureGroups (royale::Vector< royale::String > &exposureGroups) const =0

LEVEL 2 Get the list of exposure groups supported by the currently set use case.

virtual royale::CameraStatus setExposureTime (const String &exposureGroup, uint32 t exposureTime)=0

LEVEL 2 Change the exposure time for the supported operated operation modes.

 virtual royale::CameraStatus getExposureLimits (const String &exposureGroup, royale::Pair< uint32_t, uint32_t > &exposureLimits) const =0

LEVEL 2 Retrieves the minimum and maximum allowed exposure limits of the specified operation mode.

virtual royale::CameraStatus setExposureTimes (const royale::Vector< uint32_t > &exposureTimes, royale::StreamId streamId=0)=0

LEVEL 2 Change the exposure times for all sequences.

virtual royale::CameraStatus setExposureForGroups (const royale::Vector < uint32_t > &exposureTimes)=0

LEVEL 2 Change the exposure times for all exposure groups.

virtual royale::CameraStatus setProcessingParameters (const royale::ProcessingParameterVector ¶meters, uint16 t streamId=0)=0

LEVEL 2 Set/alter processing parameters in order to control the data output.

 virtual royale::CameraStatus getProcessingParameters (royale::ProcessingParameterVector ¶meters, uint16_← t streamId=0)=0

LEVEL 2 Retrieve the available processing parameters which are used for the calculation.

• virtual royale::CameraStatus registerDataListenerExtended (royale::IExtendedDataListener *listener)=0

LEVEL 2 After registering the extended data listener, extended data is sent via the callback function.

virtual royale::CameraStatus unregisterDataListenerExtended ()=0

LEVEL 2 Unregisters the data extended listener.

• virtual royale::CameraStatus setCallbackData (royale::CallbackData cbData)=0

LEVEL 2 Set the callback output data type to one type only.

virtual royale::CameraStatus setCallbackData (uint16_t cbData)=0

LEVEL 2 [deprecated] Set the callback output data type.

• virtual royale::CameraStatus setCalibrationData (const royale::String &filename)=0

LEVEL 2 Loads a different calibration from a file.

 $\bullet \ \ virtual \ royale:: Camera Status \ set Calibration Data \ (const \ royale:: Vector < uint 8_t > \&data) = 0 \\$

LEVEL 2 Loads a different calibration from a given Vector.

virtual royale::CameraStatus getCalibrationData (royale::Vector < uint8_t > &data)=0

LEVEL 2 Retrieves the current calibration data.

virtual royale::CameraStatus writeCalibrationToFlash ()=0

LEVEL 2 Tries to write the current calibration file into the internal flash of the device.

• virtual royale::CameraStatus setProcessingThreads (uint32_t numThreads, royale::StreamId streamId=0)=0

LEVEL 2 Set number of threads to be used in the processing.

virtual royale::CameraStatus writeDataToFlash (const royale::Vector< uint8_t > &data)=0

LEVEL 3 Writes an arbitrary vector of data on to the storage of the device.

• virtual royale::CameraStatus writeDataToFlash (const royale::String &filename)=0

LEVEL 3 Writes an arbitrary file to the storage of the device.

• virtual royale::CameraStatus setDutyCycle (double dutyCycle, uint16_t index)=0

LEVEL 3 Change the dutycycle of a certain sequence.

virtual royale::CameraStatus writeRegisters (const royale::Vector< royale::Pair< royale::String, uint64_t >> ®isters)=0

LEVEL 3 For each element of the vector a single register write is issued for the connected imager.

• virtual royale::CameraStatus readRegisters (royale::Vector< royale::Pair< royale::String, uint64_t >> ®isters)=0

Page: 46 of 173

API Documentation



LEVEL 3 For each element of the vector a single register read is issued for the connected imager.

- virtual royale::CameraStatus shiftLensCenter (int16_t tx, int16_t ty)=0
 - LEVEL 3 Shift the current lens center by the given translation.
- virtual royale::CameraStatus getLensCenter (uint16_t &x, uint16_t &y)=0

LEVEL 3 Retrieves the current lens center.

8.6.1 Detailed Description

This is the main interface for talking to the time-of-flight camera system.

Typically, an instance is created by the CameraManager which automatically detects a connected module. The support access levels can be activated by entering the correct code during creation. After creation, the ICameraDevice is in ready state and can be initialized.

Please refer to the provided examples (in the samples directory) for an overview on how to use this class.

On Windows please ensure that the CameraDevice object is destroyed before the main() function exits, for example by storing the unique_ptr from CameraManager::createCamera in a unique_ptr that will go out of scope at (or before) the end of main(). Not destroying the CameraDevice before the exit can lead to a deadlock ($https://stackoverflow. \leftarrow com/questions/10915233/stdthreadjoin-hangs-if-called-after-main-exits-when-using-vs2012-rc)$.

8.6.2 Constructor & Destructor Documentation

8.6.2.1 ∼ICameraDevice()

```
virtual ∼ICameraDevice ( ) [virtual]
```

8.6.3 Member Function Documentation

8.6.3.1 getAccessLevel()

LEVEL 1 Returns the current camera device access level.

8.6.3.2 getCalibrationData()

LEVEL 2 Retrieves the current calibration data.

Page: 47 of 173

API Documentation



Parameters

data Vector which will be filled with the calibration data

8.6.3.3 getCameraInfo()

Examples

sampleCameraInfo.cpp.

8.6.3.4 getCameraName()

LEVEL 1 Returns the associated camera name as a string which is defined in the CoreConfig of each module.

Examples

sampleCameraInfo.cpp.

8.6.3.5 getCurrentUseCase()

LEVEL 1 Gets the current use case as string.

Parameters

useCase | current use case identified as string

Page: 48 of 173

API Documentation



8.6.3.6 getExposureGroups()

LEVEL 2 Get the list of exposure groups supported by the currently set use case.

8.6.3.7 getExposureLimits() [1/2]

LEVEL 2 Retrieves the minimum and maximum allowed exposure limits of the specified operation mode.

Limits may vary between exposure groups. Can be used to retrieve the allowed operational range for a manual definition of the exposure time.

Parameters

exposureGroup	exposure group to be queried
exposureLimits	pair of (minimum, maximum) exposure time in microseconds

8.6.3.8 getExposureLimits() [2/2]

LEVEL 1 Retrieves the minimum and maximum allowed exposure limits of the specified operation mode.

Can be used to retrieve the allowed operational range for a manual definition of the exposure time.

For mixed-mode usecases a valid streamId must be passed. For usecases having only one stream the default value of 0 (which is otherwise not a valid stream id) can be used to refer to that stream. This is for backward compatibility.

Page: 49 of 173

API Documentation



Parameters

exposureLimits	contains the limits on successful return
streamld	stream for which the exposure limits should be returned

8.6.3.9 getExposureMode()

LEVEL 1 Retrieves the current mode of operation for acquisition of the exposure time.

For mixed-mode usecases a valid streamId must be passed. For usecases having only one stream the default value of 0 (which is otherwise not a valid stream id) can be used to refer to that stream. This is for backward compatibility.

Parameters

exposureMode	contains current exposure mode on successful return
streamId	stream for which the exposure mode should be returned

8.6.3.10 getFilterLevel()

LEVEL 1 Retrieve the level of filtering for the given streamld.

If the processing parameters do not match any of the levels this will return FilterLevel::Custom.

8.6.3.11 getFilterLevels()

LEVEL 1 Retrieve the levels of filtering that are available for the given streamld.

Page: 50 of 173

API Documentation



8.6.3.12 getFrameRate()

LEVEL 1 Get the current frame rate which is set for the current use case.

This function is not supported for mixed-mode.

8.6.3.13 getId()

LEVEL 1 Get the ID of the camera device.

Parameters

id String container in which the unique ID for the camera device will be written.

Returns

CameraStatus

Examples

sampleCameraInfo.cpp.

8.6.3.14 getLensCenter()

LEVEL 3 Retrieves the current lens center.

Parameters

Х	current x center
У	current y center

Page: 51 of 173

API Documentation



8.6.3.15 getLensParameters()

Examples

sampleCameraInfo.cpp, and sampleOpenCV.cpp.

8.6.3.16 getMaxFrameRate()

LEVEL 1 Get the maximal frame rate which can be set for the current use case.

This function is not supported for mixed-mode.

8.6.3.17 getMaxSensorHeight()

LEVEL 1 Returns the maximal height supported by the camera device.

Examples

sampleCameraInfo.cpp.

8.6.3.18 getMaxSensorWidth()

LEVEL 1 Returns the maximal width supported by the camera device.

Examples

sampleCameraInfo.cpp.

Page: 52 of 173

API Documentation



8.6.3.19 getNumberOfStreams()

LEVEL 1 Retrieves the number of streams for a specified use case.

Page: 53 of 173

API Documentation



Parameters

name	use case name
nrStreams	number of streams for the specified use case

Examples

sampleCameraInfo.cpp.

8.6.3.20 getProcessingParameters()

LEVEL 2 Retrieve the available processing parameters which are used for the calculation.

Some parameters may only be available on some devices (and may depend on both the processing implementation and the calibration data available from the device), therefore the length of the vector may be less than ProcessingFlag::NUM_FLAGS.

8.6.3.21 getStreams()

LEVEL 1 Get the streams associated with the current use case.

Examples

sample Retrieve Data.cpp.

8.6.3.22 getUseCases()

LEVEL 1 Returns all use cases which are supported by the connected module and valid for the current selected CallbackData information (e.g.

Raw, Depth, ...)

Examples

sampleCameraInfo.cpp, and sampleRetrieveData.cpp.

Page: 54 of 173

API Documentation



8.6.3.23 initialize() [1/2]

```
virtual royale::CameraStatus initialize ( ) [pure virtual]
```

LEVEL 1 Initializes the camera device and sets the first available use case.

All non-SUCCESS return statuses, except for DEVICE_ALREADY_INITIALIZED, indicate a non-recoverable error condition.

Returns

SUCCESS if the camera device has been set up correctly and the default use case has been be activated.

DEVICE_ALREADY_INITIALIZED if this is called more than once.

FILE_NOT_FOUND may be returned when this ICameraDevice represents a recording.

USECASE_NOT_SUPPORTED if the camera device was successfully opened, but the default use case could not be activated. This is only expected to happen when bringing up a new module, so it's not expected at Level 1.

CALIBRATION_DATA_ERROR if the camera device has no calibration data (or data that is incompatible with the processing, requiring a more recent version of Royale); this device can not be used with Level 1. For bringing up a new module, Level 2 access can either access the hardware by closing this instance, creating a new instance, and calling setCallback Data (CallbackData::Raw) before calling initialize() or by specifying different calibration data by calling setCalibrationData (const royale::String &filename) before calling initialize().

Other non-SUCCESS values indicate that the device can not be used.

Examples

 $sample Camera Info.cpp, \ sample Export PLY.cpp, \ sample IReplay.cpp, \ sample Open CV.cpp, \ sample Record RRF.cpp, \ and \ sample Retrieve Data.cpp.$

8.6.3.24 initialize() [2/2]

LEVEL 1 Initialize the camera and configure the system for the specified use case.

See also initialize ().

Parameters

initUseCase	identifies the use case by a case sensitive string
-------------	--

Page: 55 of 173

API Documentation



8.6.3.25 isCalibrated()

LEVEL 1 Returns the information if the camera module is calibrated.

Older camera modules can still be operated with royale, but calibration data may be incomplete.

Parameters

	calibrated	true if the module contains proper calibration data	l
--	------------	---	---

8.6.3.26 isCapturing()

LEVEL 1 Returns the information if the camera is currently in capture mode.

Parameters

capturing	true if camera is in capture mode
-----------	-----------------------------------

8.6.3.27 isConnected()

LEVEL 1 Returns the information if a connection to the camera could be established.

Parameters

connected	true if properly set up
-----------	-------------------------

Page: 56 of 173

API Documentation



8.6.3.28 readRegisters()

LEVEL 3 For each element of the vector a single register read is issued for the connected imager.

The second element of each pair will be overwritten by the value of the register given by the first element of the pair :

```
Vector<Pair<String, uint64_t» registers;
registers.push_back (Pair<String, uint64_t> ("0x0B0AD", 0));
camera->readRegisters (registers);
```

will read out the register 0x0B0AD and will replace the 0 with the current value of the register.

Parameters

registers	Contains elements of possibly not-unique (String, uint64_t) duplets. The String component can consist of: a) a
	base-10 decimal number in the range of [0, 65535] b) a base-16 hexadecimal number preceded by a "0x" in the
	range of [0, 65535]

8.6.3.29 registerDataListener()

```
\label{linear_variation} virtual \  \  \, royale:: CameraStatus \ registerDataListener \ ( \\ royale:: IDepthDataListener * \textit{listener} \ ) \  \  \, [pure virtual]
```

Examples

sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, and sampleRetrieveData.cpp.

8.6.3.30 registerDataListenerExtended()

LEVEL 2 After registering the extended data listener, extended data is sent via the callback function.

If depth data only is specified, this listener is not called. For this case, please use the standard depth data listener.

Page: 57 of 173

API Documentation



Parameters

listener	interface which needs to implement the callback method
----------	--

8.6.3.31 registerDepthImageListener()

LEVEL 1 Once registering the data listener, Android depth image data is sent via the callback function.

Consider using registerDataListener and an IDepthDataListener instead of this listener. This callback provides only an array of depth and confidence values. The mapping of pixels to the scene is similar to the pixels of a two-dimensional camera, and it is unlikely to be a rectilinear projection (although this depends on the exact camera).

Parameters

listener	interface which needs to implement the callback method
----------	--

8.6.3.32 registerDepthIRImageListener()

LEVEL 1 Once registering the data listener, depth and IR image data is sent via the callback function.

Parameters

listener	interface which needs to implement the callback method
----------	--

8.6.3.33 registerEventListener()

Page: 58 of 173

API Documentation



LEVEL 1 Register listener for event notifications.

The callback will be invoked asynchronously. Events include things like illumination unit overtemperature.

8.6.3.34 registerExposureListener() [1/2]

LEVEL 1 [deprecated] Once registering the exposure listener, new exposure values calculated by the processing are sent to the listener.

As this listener doesn't support streams, only updates for the first stream will be sent.

Only one exposure listener is supported at a time, calling this will automatically unregister any previously registered IExposureListener or IExposureListener2.

Parameters

	listener	interface which needs to implement the callback method
--	----------	--

8.6.3.35 registerExposureListener() [2/2]

LEVEL 1 Once registering the exposure listener, new exposure values calculated by the processing are sent to the listener.

Only one exposure listener is supported at a time, calling this will automatically unregister any previously registered IExposureListener or IExposureListener2.

Parameters

listener	interface which needs to implement the callback method

8.6.3.36 registerIRImageListener()

API Documentation



LEVEL 1 Once registering the data listener, IR image data is sent via the callback function.

Parameters

listener	interface which needs to implement the callback method
----------	--

8.6.3.37 registerRecordListener()

Examples

sampleRecordRRF.cpp.

8.6.3.38 registerSparsePointCloudListener()

LEVEL 1 Once registering the data listener, Android point cloud data is sent via the callback function.

Parameters

listener	interface which needs to implement the callback method
----------	--

8.6.3.39 setCalibrationData() [1/2]

LEVEL 2 Loads a different calibration from a file.

This calibration data will also be used by the processing!

Page: 60 of 173

API Documentation



Parameters

filename name of the calibration file which should be loaded

Returns

CameraStatus

8.6.3.40 setCalibrationData() [2/2]

```
\label{lem:const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const_const
```

LEVEL 2 Loads a different calibration from a given Vector.

This calibration data will also be used by the processing!

Parameters

data calibration data which should be used

Returns

CameraStatus

8.6.3.41 setCallbackData() [1/2]

LEVEL 2 Set the callback output data type to one type only.

INFO: This method needs to be called before startCapture(). If is is called while the camera is in capture mode, it will only have effect after the next stop/start sequence.

Page: 61 of 173

API Documentation



8.6.3.42 setCallbackData() [2/2]

LEVEL 2 [deprecated] Set the callback output data type.

Setting multiple types currently isn't supported.

INFO: This method needs to be called before startCapture(). If is is called while the camera is in capture mode, it will only have effect after the next stop/start sequence.

8.6.3.43 setDutyCycle()

LEVEL 3 Change the dutycycle of a certain sequence.

If the dutycycle is not supported, an error will be returned. The dutycycle can also be altered during capture mode.

Parameters

dutyCycle	dutyCycle in percent (0, 100)
index	index of the sequence to change

8.6.3.44 setExposureForGroups()

LEVEL 2 Change the exposure times for all exposure groups.

The order of the exposure times is aligned with the order of exposure groups received by getExposureGroups. If the vector that is provided is too long the extraneous values will be discard. If the vector is too short an error will be returned.

Parameters

exposureTimes	vector with exposure times in microseconds
---------------	--

Page: 62 of 173

API Documentation



8.6.3.45 setExposureMode()

LEVEL 1 Change the exposure mode for the supported operated operation modes.

For mixed-mode use cases a valid streamId must be passed. For use cases having only one stream the default value of 0 (which is otherwise not a valid stream id) can be used to refer to that stream. This is for backward compatibility.

If MANUAL exposure mode of operation is chosen, the user is able to determine set exposure time manually within the boundaries of the exposure limits of the specific operation mode.

In AUTOMATIC mode the optimum exposure settings are determined the system itself.

The default value is MANUAL.

Parameters

exposureMode	mode of operation to determine the exposure time
streamId	which stream to change exposure mode for

8.6.3.46 setExposureTime() [1/2]

LEVEL 2 Change the exposure time for the supported operated operation modes.

If MANUAL exposure mode of operation is chosen, the user is able to determine set exposure time manually within the boundaries of the exposure limits of the specific operation mode. On success the corresponding status message is returned. In any other mode of operation the method will return EXPOSURE_MODE_INVALID to indicate incompliance with the selected exposure mode. If the camera is used in the playback configuration a LOGIC_ERROR is returned instead.

Parameters

exposureGroup	exposure group to be updated
exposureTime	exposure time in microseconds

Page: 63 of 173

API Documentation



8.6.3.47 setExposureTime() [2/2]

LEVEL 1 Change the exposure time for the supported operated operation modes.

For mixed-mode use cases a valid streamId must be passed. For use cases having only one stream the default value of 0 (which is otherwise not a valid stream id) can be used to refer to that stream. This is for backward compatibility.

If MANUAL exposure mode of operation is chosen, the user is able to determine set exposure time manually within the boundaries of the exposure limits of the specific operation mode.

On success the corresponding status message is returned. In any other mode of operation the method will return EXPO SURE_MODE_INVALID to indicate non-compliance with the selected exposure mode. If the camera is used in the playback configuration a LOGIC_ERROR is returned instead.

WARNING: If this function is used on Level 3 it will ignore the limits given by the use case.

Parameters

exposureTime	exposure time in microseconds
streamId	which stream to change exposure for

Examples

sampleRetrieveData.cpp.

8.6.3.48 setExposureTimes()

LEVEL 2 Change the exposure times for all sequences.

As it is possible to reuse an exposure group for different sequences it can happen that the exposure group is updated multiple times! If the vector that is provided is too long the extraneous values will be discard. If the vector is too short an error will be returned.

WARNING: If this function is used on Level 3 it will ignore the limits given by the use case.

Page: 64 of 173

API Documentation



Parameters

exposureTimes	vector with exposure times in microseconds
streamld	which stream to change exposure times for

8.6.3.49 setExternalTrigger()

LEVEL 1 Enable or disable the external triggering.

Some camera modules support an external trigger, they can capture images synchronized with another device. If the hardware you are using supports it, calling setExternalTrigger(true) will make the camera capture images in this way. The call to set ← ExternalTrigger has to be done before initializing the device.

The external signal must not exceed the maximum FPS of the chosen UseCase, but lower frame rates are supported. If no external signal is received, the imager will not start delivering images.

For information if your camera module supports external triggering and how to use it please refer to the Getting Started Guide of your camera. If the module doesn't support triggering calling this function will return a LOGIC_ERROR.

Royale currently expects a trigger pulse, not a constant trigger signal. Using a constant trigger signal might lead to a wrong framerate!

8.6.3.50 setFilterLevel()

LEVEL 1 Change the level of filtering that is used during the processing.

This will change the setting of multiple internal filters based on some predefined levels. FilterLevel::Custom is a special setting which can not be set.

8.6.3.51 setFrameRate()

LEVEL 1 Set the frame rate to a value.

Upper bound is given by the use case. E.g. Use case with 5 FPS, a maximum frame rate of 5 and a minimum of 1 can be set. Setting a frame rate of 0 is not allowed.

The framerate is specific for the current use case. This function is not supported for mixed-mode.

Page: 65 of 173

API Documentation



8.6.3.52 setProcessingParameters()

LEVEL 2 Set/alter processing parameters in order to control the data output.

A list of processing flags is available as an enumeration. The Variant data type can take float, int, or bool. Please make sure to set the proper Variant type for the enum.

8.6.3.53 setProcessingThreads()

LEVEL 2 Set number of threads to be used in the processing.

Parameters

numThreads	Numbers of threads to be set
streamId	The ID of the current stream

8.6.3.54 setUseCase()

LEVEL 1 Sets the use case for the camera.

If the use case is supported by the connected camera device SUCCESS will be returned. Changing the use case will also change the processing parameters that are used (e.g. auto exposure)!

NOTICE: This function must not be called in the data callback - the behavior is undefined. Call it from a different thread instead.

Parameters

1	name	identifies the use case by an case sensitive string
---	------	---

Page: 66 of 173

API Documentation



Returns

SUCCESS if use case can be set

Examples

sampleRetrieveData.cpp.

8.6.3.55 shiftLensCenter()

LEVEL 3 Shift the current lens center by the given translation.

This works cumulatively (calling shiftLensCenter (0, 1) three times in a row has the same effect as calling shiftLensCenter (0, 3)). If the resulting lens center is not valid this function will return an error. This function works only for raw data readout.

Parameters

tx	translation in x direction
ty	translation in y direction

8.6.3.56 startCapture()

```
virtual royale::CameraStatus startCapture ( ) [pure virtual]
```

LEVEL 1 Starts the video capture mode (free-running), based on the specified operation mode.

A listener needs to be registered in order to retrieve the data stream. Either raw data or processed data can be consumed. If no data listener is registered an error will be returned and capturing is not started.

Examples

sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, sampleRecordRRF.cpp, and sampleRetrieveData.cpp.

Page: 67 of 173

API Documentation



8.6.3.57 startRecording()

Examples

sampleRecordRRF.cpp.

8.6.3.58 stopCapture()

```
virtual royale::CameraStatus stopCapture ( ) [pure virtual]
```

LEVEL 1 Stops the video capturing mode.

All buffers should be released again by the data listener.

Examples

sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, sampleRecordRRF.cpp, and sampleRetrieveData.cpp.

8.6.3.59 stopRecording()

```
virtual royale::CameraStatus stopRecording ( ) [pure virtual]
```

LEVEL 1 Stop recording the raw data stream into a file.

After the recording is stopped the file is available on the file system.

Examples

sampleRecordRRF.cpp.

Page: 68 of 173

API Documentation



8.6.3.60 unregisterDataListener()

```
virtual royale::CameraStatus unregisterDataListener ( ) [pure virtual]
```

LEVEL 1 Unregisters the data depth listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.61 unregisterDataListenerExtended()

```
virtual royale::CameraStatus unregisterDataListenerExtended ( ) [pure virtual]
```

LEVEL 2 Unregisters the data extended listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.62 unregisterDepthImageListener()

```
virtual royale::CameraStatus unregisterDepthImageListener ( ) [pure virtual]
```

LEVEL 1 Unregisters the depth image listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.63 unregisterDepthIRImageListener()

```
virtual royale::CameraStatus unregisterDepthIRImageListener ( ) [pure virtual]
```

LEVEL 1 Unregisters the DepthIR image listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.64 unregisterEventListener()

```
virtual royale::CameraStatus unregisterEventListener ( ) [pure virtual]
```

LEVEL 1 Unregisters listener for event notifications.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

Page: 69 of 173

API Documentation



8.6.3.65 unregisterExposureListener()

virtual royale::CameraStatus unregisterExposureListener () [pure virtual]

LEVEL 1 Unregisters the exposure listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.66 unregisterIRImageListener()

virtual royale::CameraStatus unregisterIRImageListener () [pure virtual]

LEVEL 1 Unregisters the IR image listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.67 unregisterRecordListener()

virtual royale::CameraStatus unregisterRecordListener () [pure virtual]

LEVEL 1 Unregisters the record listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.68 unregisterSparsePointCloudListener()

virtual royale::CameraStatus unregisterSparsePointCloudListener () [pure virtual]

LEVEL 1 Unregisters the sparse point cloud listener.

It's not necessary to unregister this listener (or any other listener) before deleting the ICameraDevice.

8.6.3.69 writeCalibrationToFlash()

virtual royale::CameraStatus writeCalibrationToFlash () [pure virtual]

LEVEL 2 Tries to write the current calibration file into the internal flash of the device.

If no flash is found RESOURCE_ERROR is returned. If there are errors during the flash process it will try to restore the original calibration.

This is not yet implemented for all cameras!

Some devices also store other data in the calibration data area, for example the product identifier. This L2 method will only change the calibration data, and will preserve the other data; if an unsupported combination of existing data and new data is encountered it will return an error without writing to the storage. Only the L3 methods can change or remove the additional data.

Returns

CameraStatus

Page: 70 of 173

API Documentation



8.6.3.70 writeDataToFlash() [1/2]

LEVEL 3 Writes an arbitrary file to the storage of the device.

If no flash is found RESOURCE_ERROR is returned.

Where the data will be written to is implementation defined. After using this function, the eye safety of the device is not guaranteed, even after reopening the device with L1 access. This method may overwrite the product identifier, and potentially even firmware in the device.

Parameters

filename name of the file that should be flashed

8.6.3.71 writeDataToFlash() [2/2]

LEVEL 3 Writes an arbitrary vector of data on to the storage of the device.

If no flash is found RESOURCE_ERROR is returned.

Where the data will be written to is implementation defined. After using this function, the eye safety of the device is not guaranteed, even after reopening the device with L1 access. This method may overwrite the product identifier, and potentially even firmware in the device.

Parameters

```
data data that should be flashed
```

8.6.3.72 writeRegisters()

Page: 71 of 173

API Documentation



LEVEL 3 For each element of the vector a single register write is issued for the connected imager.

Please be aware that any writes that will change crucial parts (starting the imager, stopping the imager, changing the ROI, ...) will not be reflected internally by Royale and might crash the program!

If this function is used on Level 4 (empty imager), please be aware that Royale will not start/stop the imager!

USE AT YOUR OWN RISK!!!

Parameters

registers	Contains elements of possibly not-unique (String, uint64_t) duplets. The String component can consist of: a) a
	base-10 decimal number in the range of [0, 65535] b) a base-16 hexadecimal number preceded by a "0x" in the
	range of [0, 65535]

The documentation for this class was generated from the following file:

ICameraDevice.hpp

8.7 IDepthDataListener Class Reference

Provides the listener interface for consuming depth data from Royale.

#include <IDepthDataListener.hpp>

Public Member Functions

- virtual ∼IDepthDataListener ()
- virtual void onNewData (const royale::DepthData *data)=0

Will be called on every frame update by the Royale framework.

8.7.1 Detailed Description

Provides the listener interface for consuming depth data from Royale.

A listener needs to implement this interface and register itself as a listener to the ICameraDevice.

Examples

sampleExportPLY.cpp, sampleIReplay.cpp, sampleOpenCV.cpp, and sampleRetrieveData.cpp.

Page: 72 of 173

API Documentation



8.7.2 Constructor & Destructor Documentation

8.7.2.1 ∼IDepthDataListener()

```
virtual ~IDepthDataListener ( ) [inline], [virtual]
```

8.7.3 Member Function Documentation

8.7.3.1 onNewData()

Will be called on every frame update by the Royale framework.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

Examples

sampleIReplay.cpp.

The documentation for this class was generated from the following file:

IDepthDataListener.hpp

8.8 IDepthImageListener Class Reference

Provides a listener interface for consuming depth images from Royale.

```
#include <IDepthImageListener.hpp>
```

Public Member Functions

- virtual \sim IDepthImageListener ()
- virtual void onNewData (const royale::DepthImage *data)=0

Will be called on every frame update by the Royale framework.

Page: 73 of 173

API Documentation



8.8.1 Detailed Description

Provides a listener interface for consuming depth images from Royale.

A listener needs to implement this interface and register itself as a listener to the ICameraDevice.

Consider using an IDepthDataListener instead of this listener. This callback provides only an array of depth and confidence values. The mapping of pixels to the scene is similar to the pixels of a two-dimensional camera, and it is unlikely to be a rectilinear projection (although this depends on the exact camera).

8.8.2 Constructor & Destructor Documentation

8.8.2.1 ∼IDepthImageListener()

```
virtual ~IDepthImageListener ( ) [inline], [virtual]
```

8.8.3 Member Function Documentation

8.8.3.1 onNewData()

Will be called on every frame update by the Royale framework.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

The documentation for this class was generated from the following file:

• IDepthImageListener.hpp

8.9 IDepthIRImageListener Class Reference

Provides a combined listener interface for consuming both depth and IR images from Royale.

```
#include <IDepthIRImageListener.hpp>
```

Page: 74 of 173

API Documentation



Public Member Functions

- virtual ~IDepthIRImageListener ()
- virtual void onNewData (const royale::DepthIRImage *data)=0

Will be called on every frame update by the Royale framework.

8.9.1 Detailed Description

Provides a combined listener interface for consuming both depth and IR images from Royale.

A listener needs to implement this interface and register itself as a listener to the ICameraDevice.

8.9.2 Constructor & Destructor Documentation

8.9.2.1 ~IDepthIRImageListener()

```
virtual ∼IDepthIRImageListener ( ) [inline], [virtual]
```

8.9.3 Member Function Documentation

8.9.3.1 onNewData()

Will be called on every frame update by the Royale framework.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

The documentation for this class was generated from the following file:

• IDepthIRImageListener.hpp

Page: 75 of 173

API Documentation



8.10 IEvent Class Reference

Interface for anything to be passed via IEventListener.

```
#include <IEvent.hpp>
```

Public Member Functions

- virtual ∼IEvent ()
- virtual royale::EventSeverity severity () const =0

Get the severity of this event.

• virtual const royale::String describe () const =0

Returns debugging information intended for developers using the Royale API.

• virtual royale::EventType type () const =0

Get the type of this event.

8.10.1 Detailed Description

Interface for anything to be passed via IEventListener.

8.10.2 Constructor & Destructor Documentation

8.10.2.1 ∼IEvent()

```
virtual ∼IEvent ( ) [virtual]
```

8.10.3 Member Function Documentation

Page: 76 of 173

API Documentation



8.10.3.1 describe()

```
virtual const royale::String describe ( ) const [pure virtual]
```

Returns debugging information intended for developers using the Royale API.

The strings returned may change between releases, and are unlikely to be localised, so are neither intended to be parsed automatically, nor intended to be shown to end users.

Returns

the description of this event.

8.10.3.2 severity()

```
virtual royale::EventSeverity severity ( ) const [pure virtual]
```

Get the severity of this event.

The severity of an event denotes the level of urgency the event has. The severity may be used to determine when and where an event description should be presented.

Returns

the severity of this event.

8.10.3.3 type()

```
virtual royale::EventType type ( ) const [pure virtual]
```

Get the type of this event.

Returns

the type of this event.

The documentation for this class was generated from the following file:

• IEvent.hpp

Page: 77 of 173

API Documentation



8.11 IEventListener Class Reference

This interface allows observers to receive events.

```
#include <IEventListener.hpp>
```

Public Member Functions

- virtual ROYALE_API ~IEventListener ()
- virtual ROYALE_API void onEvent (std::unique_ptr< royale::IEvent > &&event)=0
 Will be called when an event occurs.

8.11.1 Detailed Description

This interface allows observers to receive events.

8.11.2 Constructor & Destructor Documentation

8.11.2.1 \sim IEventListener()

```
virtual ROYALE_API ~IEventListener ( ) [virtual]
```

8.11.3 Member Function Documentation

8.11.3.1 onEvent()

Will be called when an event occurs.

Note there are some constraints on what the user is allowed to do in the callback.

- Actually the royale API does not claim to be reentrant (and probably isn't), so the user is not supposed to call any API function from this callback besides stopCapture
- Deleting the ICameraDevice from the callback will most certainly lead to a deadlock. This has the interesting side effect that calling exit() or equivalent from the callback may cause issues.

Page: 78 of 173

API Documentation



Parameters

The documentation for this class was generated from the following file:

· IEventListener.hpp

8.12 IExposureListener Class Reference

Provides the listener interface for handling auto-exposure updates in royale.

#include <IExposureListener.hpp>

Public Member Functions

- virtual ∼IExposureListener ()
- virtual void onNewExposure (const uint32_t exposureTime)=0

Will be called when the newly calculated exposure time deviates from currently set exposure time of the current UseCase.

8.12.1 Detailed Description

Provides the listener interface for handling auto-exposure updates in royale.

To be notified of changes to the exposure, for example to update a UI slider, an application may implement this interface and register itself as a listener to the ICameraDevice. If the application merely wishes to use auto-exposure but does not need to know that the exposure has changed, it is not necessary to implement this listener.

The exposure will be changed for future captures, but there may be another capture before the new values take effect. An application that needs the values for a specific set of captured frames should use the metadata provided as part of the capture callback, for example in DepthData::exposureTimes.

8.12.2 Constructor & Destructor Documentation

8.12.2.1 ∼IExposureListener()

virtual ~IExposureListener () [inline], [virtual]

Page: 79 of 173

API Documentation



8.12.3 Member Function Documentation

8.12.3.1 onNewExposure()

Will be called when the newly calculated exposure time deviates from currently set exposure time of the current UseCase.

Parameters

e Newly calculated expo	exposureTime
-------------------------	--------------

The documentation for this class was generated from the following file:

• IExposureListener.hpp

8.13 IExposureListener2 Class Reference

Provides the listener interface for handling auto-exposure updates in royale.

```
#include <IExposureListener2.hpp>
```

Public Member Functions

- virtual ROYALE_API \sim IExposureListener2 ()
- virtual ROYALE_API void onNewExposure (const uint32_t exposureTime, const royale::StreamId streamId)=0
 Will be called when the newly calculated exposure time deviates from currently set exposure time of the current UseCase.

8.13.1 Detailed Description

Provides the listener interface for handling auto-exposure updates in royale.

To be notified of changes to the exposure, for example to update a UI slider, an application may implement this interface and register itself as a listener to the ICameraDevice. If the application merely wishes to use auto-exposure but does not need to know that the exposure has changed, it is not necessary to implement this listener.

The exposure will be changed for future captures, but there may be another capture before the new values take effect. An application that needs the values for a specific set of captured frames should use the metadata provided as part of the capture callback, for example in DepthData::exposureTimes.

Page: 80 of 173

API Documentation



8.13.2 Constructor & Destructor Documentation

8.13.2.1 ~IExposureListener2()

```
virtual ROYALE_API ~IExposureListener2 ( ) [virtual]
```

8.13.3 Member Function Documentation

8.13.3.1 onNewExposure()

Will be called when the newly calculated exposure time deviates from currently set exposure time of the current UseCase.

Parameters

exposureTime	Newly calculated exposure time
streamId	Current stream identifier

The documentation for this class was generated from the following file:

IExposureListener2.hpp

8.14 IExtendedData Class Reference

Interface for getting additional data to the standard depth data.

#include <IExtendedData.hpp>

Page: 81 of 173

API Documentation



Public Member Functions

- virtual ∼IExtendedData ()
- virtual bool hasDepthData () const =0

Indicates if the getDepthData() has valid data.

• virtual bool hasRawData () const =0

Indicates if the getRawData() has valid data.

• virtual bool hasIntermediateData () const =0

Indicates if the getIntermediateData() has valid data.

virtual const royale::RawData * getRawData () const =0

Returns the RawData structure.

• virtual const royale::DepthData * getDepthData () const =0

Returns the DepthData structure.

• virtual const royale::IntermediateData * getIntermediateData () const =0

Returns the IntermediateData structure.

8.14.1 Detailed Description

Interface for getting additional data to the standard depth data.

The retrieval of this data requires L2 access. Please be aware that not all data is filled. Therefore, use the has* calls to check if data is provided.

8.14.2 Constructor & Destructor Documentation

8.14.2.1 ∼IExtendedData()

```
virtual ~IExtendedData ( ) [virtual]
```

8.14.3 Member Function Documentation

8.14.3.1 getDepthData()

```
virtual const royale::DepthData* getDepthData ( ) const [pure virtual]
```

Returns the **DepthData** structure.

Returns

instance of DepthData if available, nullptr else

Page: 82 of 173

API Documentation



8.14.3.2 getIntermediateData()

virtual const royale::IntermediateData* getIntermediateData () const [pure virtual]

Returns the IntermediateData structure.

Returns

instance of IntermediateData if available, nullptr else

8.14.3.3 getRawData()

```
virtual const royale::RawData* getRawData ( ) const [pure virtual]
```

Returns the RawData structure.

Returns

instance of RawData if available, nullptr else

8.14.3.4 hasDepthData()

```
virtual bool hasDepthData ( ) const [pure virtual]
```

Indicates if the getDepthData() has valid data.

If false, then the getDepthData() will return nullptr.

8.14.3.5 hasIntermediateData()

```
virtual bool hasIntermediateData ( ) const [pure virtual]
```

Indicates if the getIntermediateData() has valid data.

If false, then the getIntermediateData() will return nullptr.

Page: 83 of 173

API Documentation



8.14.3.6 hasRawData()

```
virtual bool hasRawData ( ) const [pure virtual]
Indicates if the getRawData() has valid data.
```

If false, then the getRawData() will return nullptr.

The documentation for this class was generated from the following file:

· IExtendedData.hpp

8.15 IExtendedDataListener Class Reference

```
#include <IExtendedDataListener.hpp>
```

Public Member Functions

- virtual \sim IExtendedDataListener ()=default
- virtual void onNewData (const royale::IExtendedData *data)=0
 Callback which is getting called by the ICameraDevice.

8.15.1 Constructor & Destructor Documentation

8.15.1.1 ~IExtendedDataListener()

```
virtual ~IExtendedDataListener ( ) [virtual], [default]
```

8.15.2 Member Function Documentation

8.15.2.1 onNewData()

Callback which is getting called by the ICameraDevice.

If the data is required after this call, please copy away the data, the memory block will be reused.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

Page: 84 of 173

API Documentation



Parameters

data	pointer to the underlying raw frames containing pointers to the raw frames
------	--

The documentation for this class was generated from the following file:

IExtendedDataListener.hpp

8.16 IIRImageListener Class Reference

Provides the listener interface for consuming infrared images from Royale.

```
#include <IIRImageListener.hpp>
```

Public Member Functions

- virtual ~IIRImageListener ()
- virtual void onNewData (const royale::IRImage *data)=0
 Will be called on every frame update by the Royale framework.

8.16.1 Detailed Description

Provides the listener interface for consuming infrared images from Royale.

A listener needs to implement this interface and register itself as a listener to the ICameraDevice.

8.16.2 Constructor & Destructor Documentation

8.16.2.1 ~IIRImageListener()

```
virtual ~IIRImageListener ( ) [inline], [virtual]
```

8.16.3 Member Function Documentation

Page: 85 of 173

API Documentation



8.16.3.1 onNewData()

Will be called on every frame update by the Royale framework.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

The documentation for this class was generated from the following file:

· IIRImageListener.hpp

8.17 IntermediateData Struct Reference

This structure defines the Intermediate depth data which is delivered through the callback if the user has access level 2 for the CameraDevice.

```
#include <IntermediateData.hpp>
```

Public Member Functions

• IntermediateData & operator= (const IntermediateData &dd)

Public Attributes

· int version

version number of the data format

• std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

· Streamld streamld

stream which produced the data

• uint16_t width

width of distance image

uint16_t height

height of distance image

royale::Vector < royale::IntermediatePoint > points

array of intermediate points

• royale::Vector < uint32_t > modulationFrequencies

modulation frequencies for each sequence

royale::Vector< uint32_t > exposureTimes

integration times for each sequence

• uint32_t numFrequencies

number of processed frequencies

• ProcessingParameterMap processingParameters

processing Parameters used

Page: 86 of 173

API Documentation



8.17.1 Detailed Description

This structure defines the Intermediate depth data which is delivered through the callback if the user has access level 2 for the CameraDevice.

8.17.2 Member Function Documentation

8.17.2.1 operator=()

8.17.3 Member Data Documentation

8.17.3.1 exposureTimes

```
royale::Vector<uint32_t> exposureTimes
```

integration times for each sequence

8.17.3.2 height

uint16_t height

height of distance image

8.17.3.3 modulationFrequencies

royale::Vector<uint32_t> modulationFrequencies

modulation frequencies for each sequence

Page: 87 of 173

API Documentation



8.17.3.4 numFrequencies

uint32_t numFrequencies

number of processed frequencies

8.17.3.5 points

royale::Vector<royale::IntermediatePoint> points

array of intermediate points

8.17.3.6 processingParameters

 ${\tt ProcessingParameterMap\ processingParameters}$

processing Parameters used

8.17.3.7 streamld

StreamId streamId

stream which produced the data

8.17.3.8 timeStamp

std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

Page: 88 of 173

API Documentation



8.17.3.9 version

int version

version number of the data format

8.17.3.10 width

uint16_t width

width of distance image

The documentation for this struct was generated from the following file:

• IntermediateData.hpp

8.18 IntermediatePoint Struct Reference

In addition to the standard depth point, the intermediate point also stores information which is calculated as temporaries in the processing pipeline.

#include <IntermediateData.hpp>

Public Attributes

- float distance
 - radial distance of the current pixel
- · float amplitude
 - amplitude value of the current pixel
- · float intensity
 - intensity value of the current pixel
- uint32_t flags

flag value of the current pixel

8.18.1 Detailed Description

In addition to the standard depth point, the intermediate point also stores information which is calculated as temporaries in the processing pipeline.

Distance: Radial distance for each point (in meter) Amplitude: Grayscale image that also provides a hint on the amount of reflected light. The values are positive, but the range depends on the camera that is used. Intensity: Intensity image (values can be negative in some cases) Flags: Flag image that shows invalid pixels. For a description of the flags please refer to the documentation you receive after getting level 2 access from pmd.

Page: 89 of 173

API Documentation



8.18.2 Member Data Documentation

8.18.2.1 amplitude

float amplitude

amplitude value of the current pixel

8.18.2.2 distance

float distance

radial distance of the current pixel

8.18.2.3 flags

uint32_t flags

flag value of the current pixel

8.18.2.4 intensity

float intensity

intensity value of the current pixel

The documentation for this struct was generated from the following file:

• IntermediateData.hpp

Page: 90 of 173

API Documentation



8.19 Variant::InvalidType Struct Reference

This will be thrown if a wrong type is used.

#include <Variant.hpp>

8.19.1 Detailed Description

This will be thrown if a wrong type is used.

The documentation for this struct was generated from the following file:

Variant.hpp

8.20 IPlaybackStopListener Class Reference

#include <IPlaybackStopListener.hpp>

Public Member Functions

- virtual ~IPlaybackStopListener ()=default
- virtual void onPlaybackStopped ()=0

Will be called if the playback is stopped.

8.20.1 Detailed Description

Examples

sampleExportPLY.cpp, and sampleIReplay.cpp.

8.20.2 Constructor & Destructor Documentation

8.20.2.1 ~IPlaybackStopListener()

virtual ~IPlaybackStopListener () [virtual], [default]

API Documentation



8.20.3 Member Function Documentation

8.20.3.1 onPlaybackStopped()

virtual void onPlaybackStopped () [pure virtual]

Will be called if the playback is stopped.

Examples

sampleIReplay.cpp.

The documentation for this class was generated from the following file:

• IPlaybackStopListener.hpp

8.21 IRecord Class Reference

#include <IRecord.hpp>

Inheritance diagram for IRecord:



Public Member Functions

- virtual \sim IRecord () override
- virtual bool isRecording ()=0

Indicates that recording is currently active.

 virtual void setProcessingParameters (const royale::ProcessingParameterVector ¶meters, const royale::StreamId streamId)=0

Set/alter processing parameters in order to control the data output when the recording is replayed.

• virtual void resetParameters ()=0

Resets the internal processing parameters of the recording.

• virtual void startRecord (const royale::String &filename, const std::vector< uint8_t > &calibrationData, const royale::

String &imagerSerial, const uint32_t numFrames=0, const uint32_t frameSkip=0, const uint32_t msSkip=0)=0

Page: 92 of 173

API Documentation



Starts a recording under the given filename.

• virtual void stopRecord ()=0

Stops the current recording.

• virtual bool setFrameCaptureListener (royale::collector::IFrameCaptureListener *captureListener)=0

Set/alter the current IFrameCaptureListener.

• virtual void registerEventListener (royale::IEventListener *listener)=0

Register listener for event notifications.

• virtual void unregisterEventListener ()=0

Unregisters listener for event notifications.

• virtual operator bool () const =0

bool conversion operator, returns if object is a "real" recorder or just a dummy.

8.21.1 Constructor & Destructor Documentation

8.21.1.1 ∼IRecord()

```
virtual ∼IRecord ( ) [override], [virtual]
```

8.21.2 Member Function Documentation

8.21.2.1 isRecording()

```
virtual bool isRecording ( ) [pure virtual]
```

Indicates that recording is currently active.

8.21.2.2 operator bool()

```
virtual operator bool ( ) const [pure virtual]
```

bool conversion operator, returns if object is a "real" recorder or just a dummy.

Page: 93 of 173

API Documentation



8.21.2.3 registerEventListener()

Register listener for event notifications.

8.21.2.4 resetParameters()

```
virtual void resetParameters ( ) [pure virtual]
```

Resets the internal processing parameters of the recording.

Otherwise the recording would not know when it is safe to discard old parameter sets.

8.21.2.5 setFrameCaptureListener()

Set/alter the current IFrameCaptureListener.

This can only be done if no recording is happening. If the system is recording, the listener will not be changed and false is returned.

8.21.2.6 setProcessingParameters()

Set/alter processing parameters in order to control the data output when the recording is replayed.

A list of processing flags is available as an enumeration. The Variant data type can take float, int, or bool. Please make sure to set the proper Variant type for the enum.

8.21.2.7 startRecord()

Starts a recording under the given filename.

If there is already a recording running it will be stopped and the new recording will start.

Page: 94 of 173

API Documentation



Parameters

filename	Filename which should be used
calibrationData	Calibration data used for the recording
imagerSerial	Serial number of the imager used for the recording
numFrames	Number of frames which should be recorded (0 equals infinite frames)
frameSkip	Number of frames which should be skipped after every recorded frame (0 equals all frames will be recorded)
msSkip	Time which should be skipped after every recorded frame (0 equals all frames will be recorded)

8.21.2.8 stopRecord()

virtual void stopRecord () [pure virtual]

Stops the current recording.

If no recording is running the function will return.

8.21.2.9 unregisterEventListener()

virtual void unregisterEventListener () [pure virtual]

Unregisters listener for event notifications.

The documentation for this class was generated from the following file:

· IRecord.hpp

8.22 IRecordStopListener Class Reference

This interface needs to be implemented if the client wants to get notified when recording stopped after the specified number of frames.

#include <IRecordStopListener.hpp>

Public Member Functions

- virtual ROYALE_API \sim IRecordStopListener ()
- virtual ROYALE_API void onRecordingStopped (const uint32_t numFrames)=0

Will be called if the recording is stopped.

Page: 95 of 173

API Documentation



8.22.1 Detailed Description

This interface needs to be implemented if the client wants to get notified when recording stopped after the specified number of frames.

Examples

sampleRecordRRF.cpp.

8.22.2 Constructor & Destructor Documentation

8.22.2.1 \sim IRecordStopListener()

```
virtual ROYALE_API ~IRecordStopListener ( ) [virtual]
```

8.22.3 Member Function Documentation

8.22.3.1 onRecordingStopped()

Will be called if the recording is stopped.

Parameters

numFrames Number of frames that have been recorded

Examples

sample Record RRF. cpp.

The documentation for this class was generated from the following file:

• IRecordStopListener.hpp

Page: 96 of 173

API Documentation



8.23 IReplay Class Reference

#include <IReplay.hpp>

Public Member Functions

- virtual ∼IReplay ()
- virtual royale::CameraStatus seek (const uint32_t frameNumber)=0

Seek to a different frame inside the recording.

virtual void loop (const bool restart)=0

Enable/Disable looping of the playback.

virtual void useTimestamps (const bool timestampsUsed)=0

If enabled, the playback will respect the timestamps and will pause accordingly.

• virtual uint32_t frameCount ()=0

Retrieves the number of frames in the recording.

• virtual uint32_t currentFrame ()=0

Retrieves the current frame in the recording.

• virtual void pause ()=0

Pauses the current playback.

• virtual void resume ()=0

Resumes the current playback.

• virtual void registerStopListener (royale::IPlaybackStopListener *listener)=0

Once registering the playback stop listener it will be called when the playback is stopped.

• virtual void unregisterStopListener ()=0

Unregisters the playback stop listener.

• virtual uint16_t getFileVersion ()=0

Retrieves the version of the file that was opened.

• virtual uint32_t getMajorVersion ()=0

Retrieves the build of royale that created this file.

• virtual uint32_t getMinorVersion ()=0

Retrieves the build of royale that created this file.

• virtual uint32_t getPatchVersion ()=0

Retrieves the build of royale that created this file.

• virtual uint32_t getBuildVersion ()=0

Retrieves the build of royale that created this file.

• virtual royale::CameraStatus setPlaybackRange (uint32_t first, uint32_t last)=0

Sets the playback range.

virtual void getPlaybackRange (uint32_t &first, uint32_t &last)=0

Retrieves the playback range.

8.23.1 Detailed Description

Examples

sampleExportPLY.cpp, and sampleIReplay.cpp.

Page: 97 of 173

API Documentation



8.23.2 Constructor & Destructor Documentation

8.23.2.1 ∼IReplay()

virtual ∼IReplay () [virtual]

8.23.3 Member Function Documentation

8.23.3.1 currentFrame()

virtual uint32_t currentFrame () [pure virtual]

Retrieves the current frame in the recording.

8.23.3.2 frameCount()

virtual uint32_t frameCount () [pure virtual]

Retrieves the number of frames in the recording.

8.23.3.3 getBuildVersion()

virtual uint32_t getBuildVersion () [pure virtual]

Retrieves the build of royale that created this file.

Page: 98 of 173

API Documentation



8.23.3.4 getFileVersion()

```
virtual uint16_t getFileVersion ( ) [pure virtual]
```

Retrieves the version of the file that was opened.

8.23.3.5 getMajorVersion()

```
virtual uint32_t getMajorVersion ( ) [pure virtual]
```

Retrieves the build of royale that created this file.

8.23.3.6 getMinorVersion()

```
virtual uint32_t getMinorVersion ( ) [pure virtual]
```

Retrieves the build of royale that created this file.

8.23.3.7 getPatchVersion()

```
virtual uint32_t getPatchVersion ( ) [pure virtual]
```

Retrieves the build of royale that created this file.

8.23.3.8 getPlaybackRange()

Retrieves the playback range.

8.23.3.9 loop()

Enable/Disable looping of the playback.

Page: 99 of 173

API Documentation



Parameters

restart Enable/Disable looping

Examples

sampleExportPLY.cpp.

8.23.3.10 pause()

```
virtual void pause ( ) [pure virtual]
```

Pauses the current playback.

8.23.3.11 registerStopListener()

Once registering the playback stop listener it will be called when the playback is stopped.

Parameters

listener	interface which needs to implement the callback method
----------	--

Examples

sampleIReplay.cpp.

8.23.3.12 resume()

```
virtual void resume ( ) [pure virtual]
```

Resumes the current playback.

Page: 100 of 173

API Documentation



8.23.3.13 seek()

Seek to a different frame inside the recording.

Parameters

frameNumber frame which will be read next

8.23.3.14 setPlaybackRange()

Sets the playback range.

8.23.3.15 unregisterStopListener()

```
virtual void unregisterStopListener ( ) [pure virtual]
```

Unregisters the playback stop listener.

8.23.3.16 useTimestamps()

```
virtual void useTimestamps ( {\tt const\ bool\ \it timestamps\it \it Used\ \it )} \quad \hbox{[pure\ virtual]}
```

If enabled, the playback will respect the timestamps and will pause accordingly.

Parameters

timestempelleed	Llee timestamne
timestampsUsed	Use timestamps

Page: 101 of 173

API Documentation



The documentation for this class was generated from the following file:

· IReplay.hpp

8.24 IRImage Struct Reference

Infrared image with 8Bit mono information for every pixel.

#include <IRImage.hpp>

Public Attributes

• int64_t timestamp

timestamp for the frame

· Streamld streamld

stream which produced the data

• uint16_t width

width of depth image

• uint16_t height

height of depth image

royale::Vector< uint8_t > data

8Bit mono IR image

8.24.1 Detailed Description

Infrared image with 8Bit mono information for every pixel.

8.24.2 Member Data Documentation

8.24.2.1 data

royale::Vector<uint8_t> data

8Bit mono IR image

Page: 102 of 173

API Documentation



8.24.2.2 height

uint16_t height

height of depth image

8.24.2.3 streamld

StreamId streamId

stream which produced the data

8.24.2.4 timestamp

int64_t timestamp

timestamp for the frame

8.24.2.5 width

uint16_t width

width of depth image

The documentation for this struct was generated from the following file:

• IRImage.hpp

8.25 ISparsePointCloudListener Class Reference

Provides the listener interface for consuming sparse point clouds from Royale.

#include <ISparsePointCloudListener.hpp>

Page: 103 of 173

API Documentation



Public Member Functions

- virtual ∼ISparsePointCloudListener ()
- virtual void onNewData (const royale::SparsePointCloud *data)=0

Will be called on every frame update by the Royale framework.

8.25.1 Detailed Description

Provides the listener interface for consuming sparse point clouds from Royale.

A listener needs to implement this interface and register itself as a listener to the ICameraDevice.

8.25.2 Constructor & Destructor Documentation

8.25.2.1 ∼ISparsePointCloudListener()

```
virtual ~ISparsePointCloudListener ( ) [inline], [virtual]
```

8.25.3 Member Function Documentation

8.25.3.1 onNewData()

Will be called on every frame update by the Royale framework.

NOTICE: Calling other framework functions within the data callback can lead to undefined behavior and is therefore unsupported. Call these framework functions from another thread to avoid problems.

The documentation for this class was generated from the following file:

• ISparsePointCloudListener.hpp

Page: 104 of 173

API Documentation



8.26 LensParameters Struct Reference

This container stores the lens parameters from the camera module.

#include <LensParameters.hpp>

Public Attributes

- royale::Pair< float, float > principalPoint cx/cy
- $\bullet \ \ \mathsf{royale} \\ :: \\ \mathsf{Pair} \\ < \\ \mathsf{float}, \\ \mathsf{float} \\ > \\ \mathsf{focalLength} \\$

fx/fy

- royale::Pair < float, float > distortionTangential
- royale::Vector< float > distortionRadial k1/k2/k3

8.26.1 Detailed Description

This container stores the lens parameters from the camera module.

Examples

 $sample Camera Info.cpp, \ and \ sample Open CV.cpp.$

8.26.2 Member Data Documentation

8.26.2.1 distortionRadial

royale::Vector<float> distortionRadial

k1/k2/k3

Examples

sampleCameraInfo.cpp, and sampleOpenCV.cpp.

Page: 105 of 173

API Documentation



8.26.2.2 distortionTangential

```
royale::Pair<float, float> distortionTangential p1/p2 \label{eq:p1}
```

Examples

sampleCameraInfo.cpp, and sampleOpenCV.cpp.

8.26.2.3 focalLength

```
royale::Pair<float, float> focalLength
fx/fy
```

Examples

sampleCameraInfo.cpp, and sampleOpenCV.cpp.

8.26.2.4 principalPoint

```
royale::Pair<float, float> principalPoint
cx/cy
```

Examples

sampleCameraInfo.cpp, and sampleOpenCV.cpp.

The documentation for this struct was generated from the following file:

· LensParameters.hpp

8.27 RawData Struct Reference

This structure defines the raw data which is delivered through the callback only exposed for access LEVEL 2.

#include <RawData.hpp>

Page: 106 of 173

API Documentation



Public Member Functions

- ROYALE_API RawData ()
- ROYALE_API RawData (size_t rawVectorSize)

Public Attributes

std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

· Streamld streamld

stream which produced the data

• uint16_t width

width of raw frame

• uint16_t height

height of raw frame

royale::Vector < const uint16_t * > rawData

pointer to each raw frame

 $\bullet \ \ royale:: Vector < royale:: String > {\tt exposureGroupNames}$

name of each exposure group

 $\bullet \ \ \mathsf{royale} \colon \mathsf{Vector} \! < \mathsf{size_t} > \! \mathsf{rawFrameCount}$

raw frame count of each exposure group

royale::Vector< uint32_t > modulationFrequencies

modulation frequencies for each sequence

royale::Vector < uint32_t > exposureTimes

integration times for each sequence

• float illuminationTemperature

temperature of illumination

royale::Vector< uint16_t > phaseAngles

phase angles for each raw frame

 $\bullet \ \ royale:: Vector < uint8_t > illuminationEnabled \\$

status of the illumination for each raw frame (1-enabled/0-disabled)

8.27.1 Detailed Description

This structure defines the raw data which is delivered through the callback only exposed for access LEVEL 2.

This data comprises the raw phase images coming directly from the imager.

8.27.2 Constructor & Destructor Documentation

Page: 107 of 173

API Documentation



8.27.2.1 RawData() [1/2]

```
ROYALE_API RawData ( ) [explicit]
```

8.27.2.2 RawData() [2/2]

8.27.3 Member Data Documentation

8.27.3.1 exposureGroupNames

```
royale::Vector<royale::String> exposureGroupNames
name of each exposure group
```

8.27.3.2 exposureTimes

```
royale::Vector<uint32_t> exposureTimes
```

integration times for each sequence

8.27.3.3 height

uint16_t height

height of raw frame

Page: 108 of 173

API Documentation



8.27.3.4 illuminationEnabled

royale::Vector<uint8_t> illuminationEnabled

status of the illumination for each raw frame (1-enabled/0-disabled)

8.27.3.5 illuminationTemperature

float illuminationTemperature

temperature of illumination

8.27.3.6 modulationFrequencies

royale::Vector<uint32_t> modulationFrequencies

modulation frequencies for each sequence

8.27.3.7 phaseAngles

royale::Vector<uint16_t> phaseAngles

phase angles for each raw frame

8.27.3.8 rawData

royale::Vector<const uint16_t *> rawData

pointer to each raw frame

Page: 109 of 173

API Documentation



8.27.3.9 rawFrameCount

royale::Vector<size_t> rawFrameCount

raw frame count of each exposure group

8.27.3.10 streamld

StreamId streamId

stream which produced the data

8.27.3.11 timeStamp

std::chrono::microseconds timeStamp

timestamp in microseconds precision (time since epoch 1970)

8.27.3.12 width

uint16_t width

width of raw frame

The documentation for this struct was generated from the following file:

• RawData.hpp

8.28 SparsePointCloud Struct Reference

The sparse point cloud gives XYZ and confidence for every valid point.

#include <SparsePointCloud.hpp>

Page: 110 of 173

API Documentation



Public Attributes

- int64_t timestamp timestamp for the frame
- · Streamld streamld

stream which produced the data

• uint32_t numPoints

the number of valid points

royale::Vector< float > xyzcPoints

XYZ and confidence for every valid point.

8.28.1 Detailed Description

The sparse point cloud gives XYZ and confidence for every valid point.

It is given as an array of packed coordinate quadruplets (x,y,z,c) as floating point values. The x, y and z coordinates are in meters. The confidence (c) has a floating point value in [0.0, 1.0], where 1 corresponds to full confidence.

8.28.2 Member Data Documentation

8.28.2.1 numPoints

uint32_t numPoints

the number of valid points

8.28.2.2 streamld

StreamId streamId

stream which produced the data

Page: 111 of 173

API Documentation



R	28	.2.3	timestamp
U,	.20		lillicəlallı

int64_t timestamp

timestamp for the frame

8.28.2.4 xyzcPoints

royale::Vector<float> xyzcPoints

XYZ and confidence for every valid point.

The documentation for this struct was generated from the following file:

SparsePointCloud.hpp

8.29 Variant Class Reference

Implements a variant type which can take different basic data types, the default type is int and the value is set to zero.

#include <Variant.hpp>

Classes

• struct InvalidType

This will be thrown if a wrong type is used.

Page: 112 of 173

API Documentation



Public Member Functions

- ROYALE_API Variant ()
- ROYALE_API Variant (int n, int min=std::numeric_limits< int >::lowest(), int max=std::numeric_limits< int >::max())
- ROYALE API Variant (float n, float min=std::numeric_limits< float >::lowest(), float max=std::numeric_limits< float >↔
- ROYALE_API Variant (bool n)
- ROYALE API Variant (royale::VariantType type, uint32 t value)
- ROYALE_API Variant (royale::String val, royale::Vector< royale::Pair< royale::String, int >> possibleVals)
- ROYALE_API Variant (int val, royale::Vector< royale::Pair< royale::String, int >> possibleVals)
- ROYALE_API ~Variant ()
- ROYALE_API void setFloat (float n)
- · ROYALE API float getFloat () const
- ROYALE_API float getFloatMin () const
- ROYALE_API float getFloatMax () const
 ROYALE_API void setInt (int n)
- ROYALE_API int getInt () const
- ROYALE API int getIntMin () const
- ROYALE_API int getIntMax () const
- ROYALE_API void setBool (bool n)
- ROYALE_API bool getBool () const
- ROYALE_API void setData (royale::VariantType type, uint32_t value)
- ROYALE_API uint32_t getData () const
- ROYALE_API royale::VariantType variantType () const
- ROYALE_API void setEnumValue (int val)
- ROYALE_API void setEnumValue (royale::String val)
- ROYALE API int getEnumValue () const
- ROYALE_API royale::String getEnumString () const
- ROYALE_API royale::Vector< royale::Pair< royale::String, int > > getPossibleVals () const
- ROYALE_API bool operator== (const royale::Variant &v) const
- ROYALE_API bool operator!= (const royale::Variant &v) const
- ROYALE_API bool operator < (const royale::Variant &v) const

8.29.1 Detailed Description

Implements a variant type which can take different basic data types, the default type is int and the value is set to zero.

8.29.2 Constructor & Destructor Documentation

8.29.2.1 Variant() [1/7]

ROYALE_API Variant ()

Page: 113 of 173

API Documentation



8.29.2.2 Variant() [2/7]

```
ROYALE_API Variant (
          int n,
          int min = std::numeric_limits< int >::lowest(),
          int max = std::numeric_limits< int >::max() )
```

8.29.2.3 Variant() [3/7]

8.29.2.4 Variant() [4/7]

```
ROYALE_API Variant (
          bool n )
```

8.29.2.5 Variant() [5/7]

8.29.2.6 Variant() [6/7]

Page: 114 of 173

API Documentation



8.29.2.7 Variant() [7/7]

8.29.2.8 ~Variant()

```
ROYALE_API \simVariant ( )
```

8.29.3 Member Function Documentation

8.29.3.1 getBool()

```
ROYALE_API bool getBool ( ) const
```

8.29.3.2 getData()

```
ROYALE_API uint32_t getData ( ) const
```

8.29.3.3 getEnumString()

```
ROYALE_API royale::String getEnumString ( ) const
```

8.29.3.4 getEnumValue()

```
ROYALE_API int getEnumValue ( ) const
```

Page: 115 of 173

API Documentation



8.29.3.5 getFloat()

```
ROYALE_API float getFloat ( ) const
```

8.29.3.6 getFloatMax()

```
ROYALE_API float getFloatMax ( ) const
```

8.29.3.7 getFloatMin()

```
ROYALE_API float getFloatMin ( ) const
```

8.29.3.8 getInt()

```
ROYALE_API int getInt ( ) const
```

8.29.3.9 getIntMax()

```
ROYALE_API int getIntMax ( ) const
```

8.29.3.10 getIntMin()

```
ROYALE_API int getIntMin ( ) const
```

Page: 116 of 173

API Documentation



8.29.3.11 getPossibleVals()

```
ROYALE_API royale::Vector<royale::Pair<royale::String, int> > getPossibleVals ( ) const
```

8.29.3.12 operator"!=()

8.29.3.13 operator<()

8.29.3.14 operator==()

8.29.3.15 setBool()

```
ROYALE_API void setBool (
          bool n )
```

8.29.3.16 setData()

Page: 117 of 173

API Documentation



8.29.3.17 setEnumValue() [1/2]

8.29.3.18 setEnumValue() [2/2]

8.29.3.19 setFloat()

8.29.3.20 setInt()

8.29.3.21 variantType()

```
ROYALE_API royale::VariantType variantType ( ) const
```

8.29.4 Member Data Documentation

Page: 118 of 173

API Documentation



_			-
Q	ൗവ	.4.1	h

bool b

8.29.4.2 f

float f

8.29.4.3 i

int i

The documentation for this class was generated from the following file:

• Variant.hpp

Page: 119 of 173

API Documentation



Page: 120 of 173

API Documentation



Chapter 9

File Documentation

9.1 CallbackData.hpp File Reference

Namespaces

• royale

Enumerations

• enum CallbackData: uint16_t { None = 0x00, Raw = 0x01, Depth = 0x02, Intermediate = 0x04 } Specifies the type of data which should be captured and returned as callback.

9.2 CameraAccessLevel.hpp File Reference

Namespaces

royale

Enumerations

enum CameraAccessLevel { L1 = 1, L2 = 2, L3 = 3, L4 = 4 }
 This enum defines the access level.

API Documentation



9.3 CameraManager.hpp File Reference

```
#include <memory>
#include <royale/Definitions.hpp>
#include <royale/ICameraDevice.hpp>
#include <royale/Vector.hpp>
#include <royale/String.hpp>
#include <royale/TriggerMode.hpp>
```

Classes

· class CameraManager

The CameraManager is responsible for detecting and creating instances of ICameraDevices one for each connected (supported) camera device.

Namespaces

royale

9.4 Definitions.hpp File Reference

Macros

- #define ROYALE API
- #define ADD DEBUG CONSOLE

9.4.1 Macro Definition Documentation

9.4.1.1 ADD_DEBUG_CONSOLE

#define ADD_DEBUG_CONSOLE

Page: 122 of 173

API Documentation



9.4.1.2 ROYALE_API

#define ROYALE_API

9.5 DepthData.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/StreamId.hpp>
#include <memory>
#include <cstdint>
#include <cstring>
#include <chrono>
```

Classes

struct DepthPoint

Encapsulates a 3D point in object space, with coordinates in meters.

struct DepthData

This structure defines the depth data which is delivered through the callback.

Namespaces

· royale

9.6 DepthImage.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/StreamId.hpp>
#include <memory>
#include <cstdint>
```

Classes

• struct DepthImage

The depth image represents the depth and confidence for every pixel.

Page: 123 of 173

API Documentation



Namespaces

royale

9.7 DepthIRImage.hpp File Reference

```
#include <royale/DepthImage.hpp>
#include <royale/IRImage.hpp>
```

Classes

• struct DepthIRImage

This represents combination of both depth and IR image.

Namespaces

royale

9.8 ExposureMode.hpp File Reference

Namespaces

royale

Enumerations

• enum ExposureMode { MANUAL, AUTOMATIC }

The ExposureMode is used to switch between manual and automatic exposure time handling.

9.9 FilterLevel.hpp File Reference

#include <royale/String.hpp>

Page: 124 of 173

API Documentation



Namespaces

· royale

Enumerations

```
    enum FilterLevel {
    Off = 0, Deprecated1 = 1, Deprecated2 = 2, Deprecated3 = 3,
    Deprecated4 = 4, IR1 = 5, IR2 = 6, AF1 = 7,
    CM1 = 8, Binning_1_Basic = 9, Binning_2_Basic = 10, Binning_3_Basic = 11,
    Binning_4_Basic = 12, Binning_8_Basic = 13, Binning_10_Basic = 14, Binning_1_Efficiency = 15,
    Binning_2_Efficiency = 16, Binning_3_Efficiency = 17, Binning_4_Efficiency = 18, Binning_8_Efficiency = 19,
    Binning_10_Efficiency = 20, Legacy = 200, Full = 255, Custom = 256 }
```

Royale allows to set different filter levels.

Functions

- ROYALE API royale::String getFilterLevelName (royale::FilterLevel level)
- ROYALE_API royale::FilterLevel getFilterLevelFromName (royale::String name)

9.10 ICameraDevice.hpp File Reference

```
#include <memory>
#include <royale/Status.hpp>
#include <royale/IDepthDataListener.hpp>
#include <royale/IDepthImageListener.hpp>
#include <royale/ISparsePointCloudListener.hpp>
#include <royale/IIRImageListener.hpp>
#include <royale/IDepthIRImageListener.hpp>
#include <royale/IExtendedDataListener.hpp>
#include <royale/IEventListener.hpp>
#include <royale/LensParameters.hpp>
#include <royale/ProcessingFlag.hpp>
#include <royale/CallbackData.hpp>
#include <royale/IRecordStopListener.hpp>
#include <royale/IExposureListener.hpp>
#include <royale/IExposureListener2.hpp>
#include <royale/ExposureMode.hpp>
#include <royale/FilterLevel.hpp>
#include <royale/Vector.hpp>
#include <royale/String.hpp>
#include <royale/CameraAccessLevel.hpp>
#include <royale/StreamId.hpp>
```

Page: 125 of 173

API Documentation



Classes

• class ICameraDevice

This is the main interface for talking to the time-of-flight camera system.

Namespaces

· royale

9.11 IDepthDataListener.hpp File Reference

```
#include <string>
#include <royale/DepthData.hpp>
```

Classes

· class IDepthDataListener

Provides the listener interface for consuming depth data from Royale.

Namespaces

• royale

9.12 IDepthImageListener.hpp File Reference

```
#include <string>
#include <royale/DepthImage.hpp>
```

Classes

• class IDepthImageListener

Provides a listener interface for consuming depth images from Royale.

Namespaces

• royale

Page: 126 of 173

API Documentation



9.13 IDepthIRImageListener.hpp File Reference

```
#include <string>
#include <royale/DepthIRImage.hpp>
```

Classes

• class IDepthIRImageListener

Provides a combined listener interface for consuming both depth and IR images from Royale.

Namespaces

royale

9.14 IEvent.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/String.hpp>
```

Classes

class | Event

Interface for anything to be passed via IEventListener.

Namespaces

royale

Enumerations

- enum EventSeverity { ROYALE_INFO = 0, ROYALE_WARNING = 1, ROYALE_ERROR = 2, ROYALE_FATAL = 3 } Severity of an IEvent.
- enum EventType {

ROYALE_CAPTURE_STREAM, ROYALE_DEVICE_DISCONNECTED, ROYALE_OVER_TEMPERATURE, ROYALE_RAW_FRAME_STATE ROYALE_EYE_SAFETY, ROYALE_PROCESSING, ROYALE_RECORDING, ROYALE_FRAME_DROP, ROYALE_UNKNOWN, ROYALE_ERROR_DESCRIPTION }

Type of an IEvent.

Page: 127 of 173

API Documentation



9.15 IEventListener.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <memory>
```

Classes

· class IEventListener

This interface allows observers to receive events.

Namespaces

royale

9.16 IExposureListener.hpp File Reference

```
#include <royale/Vector.hpp>
#include <royale/Definitions.hpp>
#include <royale/StreamId.hpp>
#include <cstdint>
```

Classes

· class IExposureListener

Provides the listener interface for handling auto-exposure updates in royale.

Namespaces

• royale

9.17 IExposureListener2.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/StreamId.hpp>
#include <cstdint>
```

Page: 128 of 173

API Documentation



Classes

• class IExposureListener2

Provides the listener interface for handling auto-exposure updates in royale.

Namespaces

• royale

9.18 IExtendedData.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/RawData.hpp>
#include <royale/DepthData.hpp>
#include <royale/IntermediateData.hpp>
#include <memory>
#include <cstdint>
#include <vector>
#include <chrono>
```

Classes

class IExtendedData

Interface for getting additional data to the standard depth data.

Namespaces

royale

9.19 IExtendedDataListener.hpp File Reference

```
#include <string>
#include <royale/IExtendedData.hpp>
```

Classes

• class IExtendedDataListener

Page: 129 of 173

API Documentation



Namespaces

· royale

9.20 IIRImageListener.hpp File Reference

```
#include <string>
#include <royale/IRImage.hpp>
```

Classes

· class IIRImageListener

Provides the listener interface for consuming infrared images from Royale.

Namespaces

• royale

9.21 IntermediateData.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/DepthData.hpp>
#include <royale/Vector.hpp>
#include <royale/StreamId.hpp>
#include <royale/ProcessingFlag.hpp>
#include <memory>
#include <cstdint>
#include <chrono>
```

Classes

· struct IntermediatePoint

In addition to the standard depth point, the intermediate point also stores information which is calculated as temporaries in the processing pipeline.

• struct IntermediateData

This structure defines the Intermediate depth data which is delivered through the callback if the user has access level 2 for the CameraDevice.

Page: 130 of 173

API Documentation



Namespaces

royale

9.22 IPlaybackStopListener.hpp File Reference

#include <cstdint>

Classes

· class IPlaybackStopListener

Namespaces

• royale

9.23 IRecord.hpp File Reference

```
#include <collector/IFrameCaptureListener.hpp>
#include <royale/IEventListener.hpp>
#include <royale/ProcessingFlag.hpp>
#include <royale/StreamId.hpp>
```

Classes

class IRecord

Namespaces

royale

9.24 IRecordStopListener.hpp File Reference

```
#include <cstdint>
#include <royale/Definitions.hpp>
```

Page: 131 of 173

API Documentation



Classes

• class IRecordStopListener

This interface needs to be implemented if the client wants to get notified when recording stopped after the specified number of frames.

Namespaces

royale

9.25 IReplay.hpp File Reference

```
#include <cstdint>
#include <royale/Status.hpp>
#include <royale/IPlaybackStopListener.hpp>
```

Classes

• class IReplay

Namespaces

royale

9.26 IRImage.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/StreamId.hpp>
#include <memory>
#include <cstdint>
```

Classes

• struct IRImage

Infrared image with 8Bit mono information for every pixel.

Page: 132 of 173

API Documentation



Namespaces

• royale

9.27 ISparsePointCloudListener.hpp File Reference

```
#include <string>
#include <royale/SparsePointCloud.hpp>
```

Classes

· class ISparsePointCloudListener

Provides the listener interface for consuming sparse point clouds from Royale.

Namespaces

royale

9.28 LensParameters.hpp File Reference

```
#include <royale/Pair.hpp>
#include <royale/Vector.hpp>
```

Classes

• struct LensParameters

This container stores the lens parameters from the camera module.

Namespaces

• royale

Page: 133 of 173

API Documentation



9.29 ProcessingFlag.hpp File Reference

```
#include <royale/SpectreProcessingType.hpp>
#include <royale/Variant.hpp>
#include <royale/Vector.hpp>
#include <royale/String.hpp>
```

Namespaces

- · royale
- royale::parameter

Typedefs

- typedef royale::Vector < royale::Pair < royale::ProcessingFlag, royale::Variant > > ProcessingParameterVector
 This is a map combining a set of flags which can be set/altered in access LEVEL 2 and the set value as Variant type.
- $\bullet \ \ typedef \ std::map{<} \ royale::ProcessingFlag, \ royale::Variant > ProcessingParameterMap$
- $\bullet \ \ type def \ std::pair < royale:: Processing Flag, \ royale:: Variant > Processing Parameter Pair \\$

TwoFreqCombinationType_Int, UseCorrectMPI_Bool, NUM_FLAGS }

Enumerations

enum ProcessingFlag {
 ConsistencyTolerance_Float = 0, FlyingPixelsF0_Float, FlyingPixelsF1_Float, FlyingPixelsFarDist_Float,
 FlyingPixelsNearDist_Float, LowerSaturationThreshold_Int, UpperSaturationThreshold_Int, MPIAmpThreshold_Float,
 MPIDistThreshold_Float, MPINoiseDistance_Float, NoiseThreshold_Float, AdaptiveNoiseFilterType_Int,
 AutoExposureRefAmplitude_Float, UseAdaptiveNoiseFilter_Bool, UseAutoExposure_Bool, UseRemoveFlyingPixel_Bool,
 UseMPIFlagAverage_Bool, UseMPIFlag_Amp_Bool, UseMPIFlag_Dist_Bool, UseValidateImage_Bool,
 UseRemoveStrayLight_Bool, UseSparsePointCloud_Bool, UseFilter2Freq_Bool, GlobalBinning_Int,
 UseAdaptiveBinning_Bool, AutoExposureRefValue_Float, UseSmoothingFilter_Bool, SmoothingAlpha_Float,
 SmoothingFilterType_Int, UseFlagSBI_Bool, UseHoleFilling_Bool, Reserved1,
 Reserved2, Reserved3, Reserved4, Reserved5,
 Reserved6, Reserved7, Reserved8, AutoExpoMin_Int,
 AutoExpoMax_Int, SpectreProcessingType_Int, UseGrayImageFallbackAmplitude_Bool, GrayImageMeanMap_Int,
 NoiseFilterSigmaD_Float, NoiseFilterIterations_Int, FlyingPixelAngleLimit_Float, FlyingPixelAmpThreshold_Float,
 FlyingPixelMinNeighbors_Int, FlyingPixelMaxNeighbors_Int, FlyingPixelNoiseRatioThresh_Float, SmoothingFilterResetThreshold_Float,
 CCThresh_Int, PhaseNoiseThresh_Float, StraylightThreshold_Float, NoiseFilterSigmaA_Float,

This is a list of flags which can be set/altered in access LEVEL 2 in order to control the processing pipeline.

API Documentation



Functions

- ROYALE_API royale::String getProcessingFlagName (royale::ProcessingFlag mode)
 - For debugging, printable strings corresponding to the ProcessingFlag enumeration.
- ROYALE_API bool parseProcessingFlagName (const royale::String &modeName, royale::ProcessingFlag &processing ← Flag)

Convert a string received from getProcessingFlagName back into its ProcessingFlag.

• ROYALE_API ProcessingParameterMap combineProcessingMaps (const ProcessingParameterMap &a, const ProcessingParameterMap &b)

Takes ProcessingParameterMaps a and b and returns a combination of both.

9.30 RawData.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/String.hpp>
#include <royale/StreamId.hpp>
#include <memory>
#include <cstdint>
#include <chrono>
```

Classes

struct RawData

This structure defines the raw data which is delivered through the callback only exposed for access LEVEL 2.

Namespaces

royale

9.31 README.md File Reference

9.32 SparsePointCloud.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/StreamId.hpp>
#include <memory>
#include <cstdint>
```

Page: 135 of 173

API Documentation



Classes

· struct SparsePointCloud

The sparse point cloud gives XYZ and confidence for every valid point.

Namespaces

royale

9.33 SpectreProcessingType.hpp File Reference

```
#include <royale/String.hpp>
```

Namespaces

royale

Enumerations

```
    enum SpectreProcessingType {
    AUTO = 1, CB_BINNED_WS = 2, NG = 3, AF = 4,
    CB_BINNED_NG = 5, GRAY_IMAGE = 6, CM_FI = 7, NUM_TYPES }
```

This is a list of pipelines that can be set in Spectre.

Functions

- ROYALE_API royale::String getSpectreProcessingTypeName (royale::SpectreProcessingType mode)

 Converts the given processing type into a readable string.
- ROYALE_API bool getSpectreProcessingTypeFromName (const royale::String &modeName, royale::SpectreProcessingType &processingType)

Converts the name of a processing type into an enum value.

9.34 Status.hpp File Reference

#include <royale/String.hpp>

Page: 136 of 173

API Documentation



Namespaces

royale

Enumerations

enum CameraStatus {
 SUCCESS = 0, RUNTIME_ERROR = 1024, DISCONNECTED = 1026, INVALID_VALUE = 1027,
 TIMEOUT = 1028, LOGIC_ERROR = 2048, NOT_IMPLEMENTED = 2049, OUT_OF_BOUNDS = 2050,
 RESOURCE_ERROR = 4096, FILE_NOT_FOUND = 4097, COULD_NOT_OPEN = 4098, DATA_NOT_FOUND = 4099,
 DEVICE_IS_BUSY = 4100, WRONG_DATA_FORMAT_FOUND = 4101, USECASE_NOT_SUPPORTED = 5001,
 FRAMERATE_NOT_SUPPORTED = 5002,
 EXPOSURE_TIME_NOT_SUPPORTED = 5003, DEVICE_NOT_INITIALIZED = 5004, CALIBRATION_DATA_ERROR = 5005, INSUFFICIENT_PRIVILEGES = 5006,
 DEVICE_ALREADY_INITIALIZED = 5007, EXPOSURE_MODE_INVALID = 5008, NO_CALIBRATION_DATA = 5009, INSUFFICIENT_BANDWIDTH = 5010,
 DUTYCYCLE_NOT_SUPPORTED = 5011, SPECTRE_NOT_INITIALIZED = 5012, NO_USE_CASES = 5013, NO_USE_CASES_FOR_LEVEL = 5014,
 FSM_INVALID_TRANSITION = 8096, UNKNOWN = 0x7ffffff01 }

Functions

- ROYALE_API royale::String getStatusString (royale::CameraStatus status)
 - Get a human-readable description for a given error message.
- inline ::std::ostream & operator<< (::std::ostream &os, royale::CameraStatus status)

9.35 Streamld.hpp File Reference

#include <cstdint>

Namespaces

royale

Typedefs

• using StreamId = uint16_t

The Streamld uniquely identifies a stream of measurements within a usecase.

Page: 137 of 173

API Documentation



9.36 TriggerMode.hpp File Reference

Namespaces

• royale

Enumerations

enum TriggerMode { MASTER = 0, SLAVE = 1 }
 Trigger mode used by the camera.

9.37 Variant.hpp File Reference

```
#include <royale/Definitions.hpp>
#include <royale/Vector.hpp>
#include <royale/String.hpp>
#include <limits>
#include <float.h>
#include <cstdint>
```

Classes

· class Variant

Implements a variant type which can take different basic data types, the default type is int and the value is set to zero.

struct Variant::InvalidType

This will be thrown if a wrong type is used.

Namespaces

royale

Enumerations

enum VariantType { Int, Float, Bool, Enum }

Page: 138 of 173



Chapter 10

Example Documentation

10.1 sampleCameraInfo.cpp

LEVEL 1 Retrieve further information for this specific camera. The return value is a map, where the keys are depending on the

```
\star Copyright (C) 2017 Infineon Technologies & pmdtechnologies ag
 * THIS CODE AND INFORMATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY
 * KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE
 * IMPLIED WARRANTIES OF MERCHANTABILITY AND/OR FITNESS FOR A
 * PARTICULAR PURPOSE.
#include <royale.hpp>
#include <sample_utils/EventReporter.hpp>
#include <sample_utils/PlatformResources.hpp>
int main()
    using namespace sample_utils;
    using namespace std;
     // Windows requires that the application allocate these, not the DLL.
    PlatformResources resources;
    // this represents the main camera device object
    std::unique_ptr<royale::ICameraDevice> cameraDevice;
    // the camera manager will query for a connected camera
         royale::CameraManager manager;
         sample_utils::EventReporter eventReporter;
         manager.registerEventListener (&eventReporter);
         royale::Vector<royale::String> camlist (manager.getConnectedCameraList());
cout « "Detected " « camlist.size() « " camera(s)." « endl;
bool camlistEmpty = camlist.empty();
         if (!camlistEmpty)
             cameraDevice = manager.createCamera (camlist[0]);
         // EventReporter will be deallocated before manager. So eventReporter must be
// unregistered. Declare eventReporter before manager to make the next call unnecessary.
         manager.unregisterEventListener ();
         if (camlistEmpty)
```

Page: 139 of 173

API Documentation



```
cerr « "No suitable camera device detected." « endl
#ifdef WIN32
                 \ll "Please make sure that a supported camera is plugged in and all drivers are installed" \ll
#else
                 « "Please make sure that a supported camera is plugged in and you have proper USB
      permission" « endl;
           return 1;
   // the camera device is now available and CameraManager can be deallocated here
if (cameraDevice == nullptr)
       cerr « "Cannot create the camera device" « endl;
    // IMPORTANT: call the initialize method before working with the camera device
    auto status = cameraDevice->initialize();
    if (status != royale::CameraStatus::SUCCESS)
       cerr « "Cannot initialize the camera device, error string : " « getErrorString (status) « endl;
    rovale::String id:
    royale::String name;
    uint16_t maxSensorWidth;
    uint16_t maxSensorHeight;
    status = cameraDevice->getId (id);
    if (royale::CameraStatus::SUCCESS != status)
       cerr « "failed to get ID: " « getErrorString (status) « endl;
       return 1;
    status = cameraDevice->getCameraName (name);
    if (royale::CameraStatus::SUCCESS != status)
       cerr « "failed to get name: " « getErrorString (status) « endl;
       return 1;
    status = cameraDevice->getMaxSensorWidth (maxSensorWidth);
    if (royale::CameraStatus::SUCCESS != status)
       cerr « "failed to get max sensor width: " « getErrorString (status) « endl;
       return 1;
    status = cameraDevice->getMaxSensorHeight (maxSensorHeight);
    if (royale::CameraStatus::SUCCESS != status)
       cerr « "failed to get max sensor height: " « getErrorString (status) « endl;
       return 1;
    royale::Vector<royale::String> useCases;
    status = cameraDevice->getUseCases (useCases);
    if (royale::CameraStatus::SUCCESS != status)
       cerr « "failed to get available use cases: " « getErrorString (status) « endl;
       return 1;
    royale::Vector<royale::Pair<royale::String, royale::String» cameraInfo;</pre>
    status = cameraDevice->getCameraInfo (cameraInfo);
    if (rovale::CameraStatus::SUCCESS != status)
       cerr « "failed to get camera info: " « getErrorString (status) « endl;
    \ensuremath{//}\xspace display some information about the connected camera
    cout « "======= " « endl;
    cout « "
                   Camera information"
                                                   « endl:
```

Page: 140 of 173

API Documentation



```
cout « "-----" « endl;
for (size_t i = 0; i < useCases.size(); ++i)</pre>
    cout « listIndent « useCases[i] « endl;
    uint32_t streamCount = 0;
    status = cameraDevice->getNumberOfStreams (useCases[i], streamCount);
    if (royale::CameraStatus::SUCCESS == status && streamCount > 1)
         cout « noteIndent « "this operation mode has " « streamCount « " streams" « endl;
cout « "CameraInfo items: " « cameraInfo.size() « endl;
for (size_t i = 0; i < cameraInfo.size(); ++i)</pre>
    cout « listIndent « cameraInfo[i] « endl;
royale::LensParameters lens;
status = cameraDevice->getLensParameters (lens);
if (royale::CameraStatus::SUCCESS != status)
    cerr « "failed to get lens parameters: " « getErrorString (status) « endl;
cout « "Lens focal length: " « lens.focalLength.first « " / " « lens.focalLength.second « endl; cout « "Principal point: " « lens.principalPoint.first « " / " « lens.principalPoint.second « endl; cout « "Distortion tangential: " « lens.distortionTangential.first « " / " «
   lens.distortionTangential.second « endl;
cout « "Distortion radial: ";
for (auto curK : lens.distortionRadial)
   cout « curK « " / ";
cout « endl;
```

10.2 sampleExportPLY.cpp

LEVEL 1 Once registering a record listener, the listener gets notified once recording has stopped after specified frames.

Parameters

listener interface which needs to implement the callback method

Page: 141 of 173

API Documentation



```
#include <chrono>
#include <mutex>
#include <fstream>
#include <sstream>
#include <string>
#include <royale.hpp>
#include <royale/IPlaybackStopListener.hpp>
#include <royale/IReplay.hpp>
using namespace std;
namespace
     class MyListener : public royale::IDepthDataListener
     public:
          MyListener (string rrfFile, uint32_t numFrames) :
              m_frameNumber (0),
                m_numFrames (numFrames),
                m_rrfFile (std::move (rrfFile))
          void writePLY (const string &filename, const royale::DepthData *data)
                // For an explanation of the PLY file format please have a look at
                // https://en.wikipedia.org/wiki/PLY_(file_format)
                ofstream outputFile;
                stringstream stringStream;
                outputFile.open (filename, ofstream::out);
                if (outputFile.fail())
                     cerr « "Outputfile " « filename « " could not be opened!" « endl;
                     return;
               else
                     // if the file was opened successfully write the PLY header stringStream \ll "ply" \ll endl; stringStream \ll "format ascii 1.0" \ll endl;
                    stringStream « "format ascil 1.0" « endl;
stringStream « "comment Generated by sampleExportPLY" « endl;
stringStream « "element vertex " « data->points.size() « endl;
stringStream « "property float x" « endl;
stringStream « "property float z" « endl;
stringStream « "element face 0" « endl;
stringStream « "element face 0" « endl;
                     stringStream « "property list uchar int vertex_index" « endl; stringStream « "end_header" « endl;
                     // output XYZ coordinates into one line
                     for (size_t i = 0; i < data->points.size(); ++i)
                          stringStream « data->points.at (i).x « " " « data->points.at (i).y « " " «
         data->points.at (i).z « endl;
                     // output stringstream to file and close it
                     outputFile « stringStream.str();
                     outputFile.close();
          void onNewData (const royale::DepthData *data) override
                stringstream filename;
               m_frameNumber++;
               cout « "Exporting frame " « m_frameNumber « " of " « m_numFrames « endl;
filename « m_frameNumber « ".ply";
writePLY (filename.str(), data);
     private:
          uint32_t m_frameNumber; // The current frame number
          uint32_t m_numFrames; // Total number of frames in the recording string m_rrfFile; // Recording file that was opened
     class MyPlaybackStopListener : public royale::IPlaybackStopListener
```

Page: 142 of 173

API Documentation



```
public:
        MyPlaybackStopListener()
             m_playbackRunning = true;
         void onPlaybackStopped() override
             lock_guard<mutex> lock (m_stopMutex);
             m_playbackRunning = false;
        void waitForStop()
             bool running = true;
             {
                      lock_guard<mutex> lock (m_stopMutex);
                       running = m_playbackRunning;
                  this_thread::sleep_for (chrono::milliseconds (50));
             while (running);
    private:
                                  // Mutex to synchronize the access to m_playbackRunning
        mutex m stopMutex:
        bool m_playbackRunning; // Shows if the playback is still running
int main (int argc, char *argv[])
    // This is the data listener which will receive callbacks. It's declared
    // his is the data listened which will receive callbacks. It declared // before the camerabevice so that, if this function exits with a 'return' // statement while the camera is still capturing, it will still be in scope
    // until the cameraDevice's destructor implicitly deregisters the listener.
    unique_ptr<MyListener> listener;
    // PlaybackStopListener which will be called as soon as the playback stops.
    MyPlaybackStopListener stopListener;
    // Royale's API treats the .rrf file as a camera, which it captures data from.
unique_ptr<royale::ICameraDevice> cameraDevice;
    // check the command line for a given file
    if (argc < 2)
        cout « "Usage " « argv[0] « " rrfFileToExport" « endl;
        cout « endl;
        cout « "Each frame of the recording is saved as a separate .ply file " « endl; cout « "in the current directory." « endl;
    // Use the camera manager to open the recorded file, this block scope is because we can allow
    // the CameraManager to go out of scope once the file has been opened.
        royale::CameraManager manager;
         // create a device from the file
         cameraDevice = manager.createCamera (argv[1]);
    ^{\prime\prime} // if the file was loaded correctly the camera
Device is now available
    if (cameraDevice == nullptr)
        cerr « "Cannot load the file " « argv[1] « endl;
    // cast the cameraDevice to IReplay which offers more options for playing
    // back recordings
    auto replayControls = dynamic_cast<royale::IReplay *> (cameraDevice.get());
    if (replayControls == nullptr)
        cerr « "Unable to cast to IReplay interface" « endl;
        return 1;
```

Page: 143 of 173

API Documentation



```
// IMPORTANT: call the initialize method before working with the camera device
if (cameraDevice->initialize() != royale::CameraStatus::SUCCESS)
    cerr « "Cannot initialize the camera device" « endl;
^{\prime} // turn off the looping of the playback
replayControls->loop (false);
// Turn off the timestamps to speed up the conversion. If timestamps are enabled, an .rrf that
// was recorded at 5FPS will generate callbacks to onNewData() at only 5 callbacks per second.
replayControls->useTimestamps (false);
// retrieve the total number of frames from the recording
auto numFrames = replayControls->frameCount();
// Create and register the data listener
listener.reset (new MyListener (argv[1], numFrames));
if (cameraDevice->registerDataListener (listener.get()) != royale::CameraStatus::SUCCESS)
    cerr « "Error registering data listener" « endl;
    return 1;
// register a playback stop listener. This will be called as soon
// as the file has been played back once (because loop is turned off)
replayControls->registerStopListener (&stopListener);
  start capture mode
if (cameraDevice->startCapture() != royale::CameraStatus::SUCCESS)
    cerr « "Error starting the capturing" « endl;
    return 1;
// block until the playback has finished
stopListener.waitForStop();
// stop capture mode
if (cameraDevice->stopCapture() != royale::CameraStatus::SUCCESS)
    cerr « "Error stopping the capturing" « endl;
return 0;
```

10.3 samplelReplay.cpp

Class that can be used to get more control over the playback of a recording. To access the interface the ICameraDevice has to be casted to an IReplay object.

Page: 144 of 173

API Documentation



```
std::cout « "received a stop signal from the IReplay interface\n";
        }
    };
    class MyDepthDataListener : public royale::IDepthDataListener
        void onNewData (const royale::DepthData *data) override
            std::cout « "received depth data with time_stamp: " « data->timeStamp.count() « '\n';
    };
int main (int argc, char *argv[])
    // We receive our RRF-File from the command line.
    if (argc < 2)
        std::cerr « "Wrong usage of this sample! Please pass an RRF-File as first parameter.\n";
        return -1;
    auto rrf_file = argv[1];
      This represents the main camera device object.
    std::unique_ptr<royale::ICameraDevice> camera;
        // The camera manager can be created locally.
        // It is only used to create a camera device object
        // and can be destroyed afterwards.
        royale::CameraManager manager{};
        camera = manager.createCamera (rrf_file);
    // We have to check if the camera device was created successfully.
    if (camera == nullptr)
        std::cerr \boldsymbol{\mathsf{w}} "Can not create the camera! This may be caused by passing a bad RRF-File.\n";
        return -2;
    // Before the camera device is ready we have to invoke initialize on it.
    if (camera->initialize() != royale::CameraStatus::SUCCESS)
        std::cerr « "Camera can not be initialized!\n";
        return -3;
    // Now that the camera is ready we create our IDepthDataListener
    // and register it to the camera device.
    MyDepthDataListener depth_data_listener{};
    camera->registerDataListener (&depth_data_listener);
// As we know that the camera device was created using a RRF-File
    // we can expect that the underlying object implements IReplay.
    // To use this interface we can dynamic_cast the object to an IReplay object.
    auto replay = dynamic_cast<royale::IReplay *> (camera.get());
if (replay == nullptr)
        std::cerr « "Can not cast the camera into an IReplay object!\n";
    // Now that we have access to the IReplay interface we can register
    // our IReplayStopListener.
    MyPlaybackStopListener playback_stop_listener{};
    replay->registerStopListener (&playback_stop_listener);
      In the next step we set the current
    // frame of the replay object to its last one.
    \ensuremath{//} We also set the replay not to loop its frames.
    \ensuremath{//} This means that only the last frame will be played when the camera starts capturing.
```

Page: 145 of 173

API Documentation



```
auto frame_count = replay->frameCount();
replay->seek (frame_count - 1);
replay->loop (false);
// Here starts the first demonstrating part of this sample.
// If the replay behaves as we defined, the camera
\ensuremath{//} will only capture one depth data before it stops capturing.
std::cout « "start playback...\n";
camera->startCapture();
std::this_thread::sleep_for (std::chrono::seconds{ 6 });
camera->stopCapture();
std::cout « "stopped playback.\n";
// In the next step we set the current
// frame of the replay object to its last one.
// We also set the replay to loop its frames.
// This means that the play will start at the same
// frame as before but this time the replay will loop its content.
replay->seek (frame_count - 1);
replay->loop (true);
// Here starts the second demonstrating part of this sample.
// If the replay behaves as we defined, the camera
// will capture multiple depth data.
^{\prime\prime} // We also pause and resume the playback here after 2 and 4 seconds.
// Therefor the camera should capture depth data in the first two seconds,
// then stop capture data for two seconds and
// then continue capture data for two more seconds.
std::cout « "start playback...\n";
camera->startCapture();
std::this_thread::sleep_for (std::chrono::seconds{ 2 });
replay->pause();
std::this_thread::sleep_for (std::chrono::seconds{ 2 });
std::this_thread::sleep_for (std::chrono::seconds{ 2 });
camera->stopCapture();
std::cout « "stopped playback.\n";
// In the next step we set the current frame of the
// replay object to its first one.
// We also set the replay not to use timestamps.
\ensuremath{//} This has the effect that the Replay will not try to
// send the frames with the original fps but as fast as possible.
replay->seek (0);
replay->useTimestamps (false);
   Here starts the third demonstrating part of this sample.
// If the replay behaves as we defined, the camera
// will capture multiple depth data much faster as in the demonstration before.
std::cout « "start playback...\n";
camera->startCapture();
std::this_thread::sleep_for (std::chrono::seconds{ 2 });
camera->stopCapture();
std::cout « "stopped playback.\n";
return 0;
```

10.4 sampleOpenCV.cpp

LEVEL 1 Gets the intrinsics of the camera module which are stored in the calibration file

Page: 146 of 173

API Documentation



Parameters

param LensParameters is storing all the relevant information (c,f,p,k)

Returns

CameraStatus

```
/****************************
* Copyright (C) 2017 Infineon Technologies & pmdtechnologies ag
 \star THIS CODE AND INFORMATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY
 \star KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE
 * IMPLIED WARRANTIES OF MERCHANTABILITY AND/OR FITNESS FOR A
 * PARTICULAR PURPOSE.
 #include <royale.hpp>
#include <iostream>
#include <mutex>
#include <opencv2/opencv.hpp>
#include <sample_utils/PlatformResources.hpp>
using namespace royale;
using namespace sample_utils;
using namespace std;
using namespace cv;
// Linker errors for the OpenCV sample
// If this example gives linker errors about undefined references to cv::namedWindow and cv::imshow,
// or QFontEngine::glyphCache and qMessageFormatString (from OpenCV to Qt), it may be caused by a
// change in the compiler's C++ ABI.
// With Ubuntu and Debian's distribution packages, the libopency packages that have 'v5' at the end // of their name, for example libopency-video2.4v5, are compatible with GCC 5 (and GCC 6), but
// incompatible with GCC 4.8 and GCC 4.9. The -dev packages don't have the postfix, but depend on
// the v5 (or non-v5) version of the corresponding lib package. When Ubuntu moves to OpenCV 3.0,
// they're likely to drop the postfix (but the packages will be for GCC 5 or later).
// If you are manually installing OpenCV or Qt, you need to ensure that the binaries were compiled // with the same version of the compiler. The version number of the packages themselves doesn't say // which ABI they use, it depends on which version of the compiler was used.
class MyListener : public IDepthDataListener
public :
    MvListener():
        undistortImage (false)
    void onNewData (const DepthData *data)
        // this callback function will be called for every new
        // depth frame
        std::lock_guard<std::mutex> lock (flagMutex);
        // create two images which will be filled afterwards
         // each image containing one 32Bit channel
        zImage.create (Size (data->width, data->height), CV_32FC1);
        grayImage.create (Size (data->width, data->height), CV_32FC1);
        // set the image to zero
        zImage = Scalar::all (0);
        grayImage = Scalar::all (0);
         int k = 0;
        for (int y = 0; y < zImage.rows; y++)</pre>
             float *zRowPtr = zImage.ptr<float> (y);
             float *grayRowPtr = grayImage.ptr<float> (y);
             for (int x = 0; x < zImage.cols; x++, k++)
```

Page: 147 of 173

API Documentation



```
auto curPoint = data->points.at (k);
                  if (curPoint.depthConfidence > 0)
                       // if the point is valid, map the pixel from 3D world
                       // coordinates to a 2D plane (this will distort the image)
                       zRowPtr[x] = adjustZValue (curPoint.z);
                      grayRowPtr[x] = adjustGrayValue (curPoint.grayValue);
             }
         // create images to store the 8Bit version (some OpenCV
         // functions may only work on 8Bit images)
        zImage8.create (Size (data->width, data->height), CV_8UC1);
grayImage8.create (Size (data->width, data->height), CV_8UC1);
         // convert images to the 8Bit version
         // This sample uses a fixed scaling of the values to (0, 255) to avoid flickering.
         // You can also replace this with an automatic scaling by using
         // normalize(zImage, zImage8, 0, 255, NORM_MINMAX, CV_8UC1)
        // normalize(grayImage, grayImage8, 0, 255, NORM_MINMAX, CV_8UC1)
zImage.convertTo (zImage8, CV_8UC1);
grayImage.convertTo (grayImage8, CV_8UC1);
            (undistortImage)
              \ensuremath{//} call the undistortion function on the z image
             Mat temp = zImage8.clone();
undistort (temp, zImage8, cameraMatrix, distortionCoefficients);
         // scale and display the depth image
         scaledZImage.create (Size (data->width * 4, data->height * 4), CV_8UC1);
        resize (zImage8, scaledZImage, scaledZImage.size());
imshow ("Depth", scaledZImage);
         if (undistortImage)
              // call the undistortion function on the gray image
             Mat temp = grayImage8.clone();
             undistort (temp, grayImage8, cameraMatrix, distortionCoefficients);
         // scale and display the gray image scaledGrayImage.create (Size (data->width * 4, data->height * 4), CV_8UC1);
         resize (grayImage8, scaledGrayImage, scaledGrayImage.size());
         imshow ("Gray", scaledGrayImage);
    void setLensParameters (const LensParameters &lensParameters)
         // Construct the camera matrix
         // (fx 0
// (0 fy
// (0 0
                        cx)
                        cy)
         cameraMatrix = (Matld (3, 3) « lensParameters.focalLength.first, 0,
        lensParameters.principalPoint.first,
                          0, lensParameters.focalLength.second, lensParameters.principalPoint.second,
0, 0, 1);
         // Construct the distortion coefficients
         // k1 k2 p1 p2 k3
         distortionCoefficients = (Matld (1, 5) « lensParameters.distortionRadial[0],
                                      lensParameters.distortionRadial[1],
                                      {\tt lensParameters.distortionTangential.first,}
                                       lensParameters.distortionTangential.second.
                                      lensParameters.distortionRadial[2]);
    void toggleUndistort()
         std::lock guard<std::mutex> lock (flagMutex);
        undistortImage = !undistortImage;
private:
    // adjust z value to fit fixed scaling, here max dist is 2.5m
    // the max dist here is used as an example and can be modified
    float adjustZValue (float zValue)
```

API Documentation



```
float clampedDist = std::min (2.5f, zValue);
         float newZValue = clampedDist / 2.5f * 255.0f;
         return newZValue;
    ^{\prime\prime} adjust gray value to fit fixed scaling, here max value is 180
    // the max value here is used as an example and can be modified
float adjustGrayValue (uint16_t grayValue)
         float clampedVal = std::min (180.0f, grayValue * 1.0f);
         float newGrayValue = clampedVal / 180.f * 255.0f;
         return newGrayValue;
    // define images for depth and gray
// and for their 8Bit and scaled versions
    Mat zImage, zImage8, scaledZImage;
    Mat grayImage, grayImage8, scaledGrayImage;
    // lens matrices used for the undistortion of
    // the image
    Mat cameraMatrix;
    Mat distortionCoefficients;
    std::mutex flagMutex;
    bool undistortImage;
int main (int argc, char *argv[])
    // Windows requires that the application allocate these, not the DLL.
    PlatformResources resources;
    // This is the data listener which will receive callbacks. It's declared
    // before the cameraDevice so that, if this function exits with a 'return' // statement while the camera is still capturing, it will still be in scope
    // until the cameraDevice's destructor implicitly de-registers the listener.
    MyListener listener;
// this represents the main camera device object
    std::unique_ptr<ICameraDevice> cameraDevice;
    // the camera manager will query for a connected camera
         CameraManager manager;
         // check the number of arguments
         if (argc > 1)
              // if the program was called with an argument try to open this as a file
              cout « "Trying to open : " « argv[1] « endl;
              cameraDevice = manager.createCamera (argv[1]);
         else
              // if no argument was given try to open the first connected camera
royale::Vector<royale::String> camlist (manager.getConnectedCameraList());
cout « "Detected " « camlist.size() « " camera(s)." « endl;
              if (!camlist.empty())
                   cameraDevice = manager.createCamera (camlist[0]);
              }
              else
                   cerr « "No suitable camera device detected." « endl
                        "Please make sure that a supported camera is plugged in, all drivers are "
"installed, and you have proper USB permission" « endl;
                   return 1;
              camlist.clear();
    // the camera device is now available and CameraManager can be deallocated here
    if (cameraDevice == nullptr)
         // no cameraDevice available
         if (argc > 1)
         {
              cerr « "Could not open " « argv[1] « endl;
```

Page: 149 of 173

API Documentation



```
return 1:
         cerr « "Cannot create the camera device" « endl;
         return 1;
// IMPORTANT: call the initialize method before working with the camera device
auto status = cameraDevice->initialize();
if (status != CameraStatus::SUCCESS)
    \texttt{cerr} \, \twoheadleftarrow \, \texttt{"Cannot initialize the camera device, error string : " \, \twoheadleftarrow \, \texttt{getErrorString (status)} \, \twoheadleftarrow \, \texttt{endl;}
    return 1:
// retrieve the lens parameters from Royale
LensParameters lensParameters;
status = cameraDevice->getLensParameters (lensParameters);
if (status != CameraStatus::SUCCESS)
    cerr « "Can't read out the lens parameters" « endl;
listener.setLensParameters (lensParameters);
// register a data listener
if (cameraDevice->registerDataListener (&listener) != CameraStatus::SUCCESS)
    cerr « "Error registering data listener" « endl;
// create two windows
namedWindow ("Depth", WINDOW_AUTOSIZE);
namedWindow ("Gray", WINDOW_AUTOSIZE);
// start capture mode
if (cameraDevice->startCapture() != CameraStatus::SUCCESS)
    cerr « "Error starting the capturing" « endl;
    return 1;
int currentKey = 0;
while (currentKey != 27)
    // wait until a key is pressed
    currentKey = waitKey (0) & 255;
if (currentKey == 'd')
    {
           / toggle the undistortion of the image
         listener.toggleUndistort();
// stop capture mode
if (cameraDevice->stopCapture() != CameraStatus::SUCCESS)
    cerr « "Error stopping the capturing" « endl;
    return 1;
return 0;
```

10.5 sampleRecordRRF.cpp

LEVEL 1 Start recording the raw data stream into a file. The recording will capture the raw data coming from the imager. If frameSkip and msSkip are both zero every frame will be recorded. If both are non-zero the behavior is implementation-defined.

Page: 150 of 173

API Documentation



Parameters

fileName	full path of target filename (proposed suffix is .rrf)
numberOfFrames	indicate the maximal number of frames which should be captured (stop will be called automatically). If zero (default) is set, recording will happen till stopRecording is called.
frameSkip	indicate how many frames should be skipped after every recorded frame. If zero (default) is set and msSkip is zero, every frame will be recorded.
msSkip	indicate how many milliseconds should be skipped after every recorded frame. If zero (default) is set and frameSkip is zero, every frame will be recorded.

```
/**************************
 \star Copyright (C) 2018 Infineon Technologies & pmdtechnologies ag
 * THIS CODE AND INFORMATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY
 * KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE
 * IMPLIED WARRANTIES OF MERCHANTABILITY AND/OR FITNESS FOR A
 * PARTICULAR PURPOSE.
 #include <rovale.hpp>
#include <sample_utils/PlatformResources.hpp>
#include <condition_variable>
#include <mutex>
#include <memory>
#include <iostream>
#include <cstdint>
  This is a standard implementation for handling an error on the camera device.
// In other applications it might be a better idea to retry some of the methods
// but for this sample this should be enough.
\verb|#define CHECKED_CAMERA_METHOD (METHOD_TO_INVOKE) \setminus \\
do\
   auto status = METHOD_TO_INVOKE; \
    if (royale::CameraStatus::SUCCESS != status) \
       return -1;\
} while (0)
namespace
    std::mutex mtx;
   std::matex mex,
std::condition_variable condition;
bool notified = false;
    class MyRecordListener : public royale::IRecordStopListener
    public:
       void onRecordingStopped (const uint32_t numFrames) override
           std::cout « "The onRecordingStopped was invoked with numFrames=" « numFrames « std::endl;
           // Notify the main method to return
           std::unique_lock<std::mutex> lock (mtx);
           notified = true;
           condition.notify_all();
    MyRecordListener myRecordListener;
int main (int argc, char **argv)
    // Receive the parameters to capture from the command line:
    if (2 > argc)
```

Page: 151 of 173

API Documentation



```
std::cout « "There are no parameters specified! Use:" « std::endl
             « argv[0] « " C:/path/to/file.rrf [numberOfFrames [framesToSkip [msToSkip]]]" « std::endl;
royale::String file (argv[1]);
auto numberOfFrames = argc >= 3 ? std::stoi (argv[2]) : 0;
auto framesToSkip = argc >= 4 ? std::stoi (argv[3]) : 0;
auto msToSkip = argc >= 5 ? std::stoi (argv[4]) : 0;

// If the first argument was "--help", don't treat that as a filename
if (file == "--help" || file == "-h" || file == "/?")
    std::cout « argv[0] « ":" « std::endl;
    std::cout « "--help, -h, /? : this help" « std::endl;
   std::cout « std::endl; std::cout « argv[0] « " C:/path/to/file.rrf [numberOfFrames [framesToSkip [msToSkip]]]" « std::endl;
   std::cout « "Record to the given RRF file, overwriting it if it already exists" « std::endl;
^{\prime\prime} // Print the parsed parameters to the command line
« "framesToSkip=" « framesToSkip « std::endl
sample utils::PlatformResources platformResources;
std::unique_ptr<royale::ICameraDevice> cameraDevice;
// The camera manager will query for a connected camera.
    royale::CameraManager manager;
   auto connectedCameraList = manager.getConnectedCameraList();
    if (0 >= connectedCameraList.count())
        std::cout « "There is no camera connected!" « std::endl;
        return -1;
    cameraDevice = manager.createCamera (connectedCameraList[0]);
^{\prime} // The camera device is now available and CameraManager can be deallocated here.
if (nullptr == cameraDevice)
    std::cout « "The camera can not be created!" « std::endl;
// IMPORTANT: call the initialize method before working with the camera device
CHECKED_CAMERA_METHOD (cameraDevice->initialize());
// If the user specified a number of frames to capture we use a listener to tidy up
// the camera afterwards.
if (0 < numberOfFrames)</pre>
    CHECKED_CAMERA_METHOD (cameraDevice->registerRecordListener (&myRecordListener));
    CHECKED_CAMERA_METHOD (cameraDevice->startCapture());
    CHECKED_CAMERA_METHOD (cameraDevice->startRecording (file, static_cast<uint32_t> (numberOfFrames),
                                                           static_cast<uint32_t> (framesToSkip),
  msToSkip));
    // It is important not to close the main method before // the record stop callback was received!
   std::unique_lock<std::mutex> lock (mtx);
    // loop to avoid spurious wakeups
    while (!notified)
        condition.wait (lock);
   auto status = cameraDevice->stopCapture();
    if (royale::CameraStatus::SUCCESS != status)
        std::cout « "Failed to close the camera device with status="
                  « royale::getStatusString (status).c_str()
                  « std::endl;
    }
```

Page: 152 of 173

API Documentation



10.6 sampleRetrieveData.cpp

LEVEL 1 Once registering the data listener, 3D point cloud data is sent via the callback function.

Parameters

listener interface which needs to implement the callback method

```
\star Copyright (C) 2017 Infineon Technologies & pmdtechnologies ag
 * THIS CODE AND INFORMATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY
 * KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE
 * IMPLIED WARRANTIES OF MERCHANTABILITY AND/OR FITNESS FOR A
 * PARTICULAR PURPOSE.
 #include <royale.hpp>
#include <algorithm>
#include <iomanip>
#include <iostream>
#include <thread>
#include <mutex>
#include <chrono>
#include <sample_utils/PlatformResources.hpp>
using namespace sample_utils;
using namespace std;
class MyListener : public royale::IDepthDataListener
    static const size_t MAX_HEIGHT = 40;
   static const size_t MAX_WIDTH = 76;
char asciiPoint (const royale::DepthData *data, std::size_t x, std::size_t y)
        // Using a bounds-check here is inefficient, but allows the scale-to-max-width-or-height
        // loop in onNewData to be simpler.
        if (x \ge data - width || y \ge data - height)
           return ' ';
        auto depth = data->points[y * data->width + x];
        if (depth.depthConfidence < 128)</pre>
           return ' ':
       const royale::Vector<royale::Pair<float, char» DEPTH_LETTER
```

Page: 153 of 173

API Documentation



```
{0.25f, '0'},
             {0.30f, 'o'},
{0.35f, '+'},
             {0.40f, '-'},
             {1.00f, '.'},
         for (auto i : DEPTH LETTER)
             if (depth.z < i.first)</pre>
                 return i.second;
         return ' ';
    struct MyFrameData
         std::vector<uint32_t> exposureTimes;
         std::vector<std::string> asciiFrame;
    };
public:
    void onNewData (const royale::DepthData *data) override
         \ensuremath{//} Demonstration of how to retrieve the exposure times for the current stream. This is a
         // vector which can contain several numbers, because the depth frame is calculated from
         // several individual raw frames.
         auto exposureTimes = data->exposureTimes;
         // The data pointer will become invalid after onNewData returns. When processing the data,
         // it's necessary to either:
         // 1. Do all the processing before this method returns, or
         // 2. Copy the data (not just the pointer) for later processing, or
         // 3. Do processing that needs the full data here, and generate or copy only the data required for later processing
         // The Royale library's depth-processing thread may block while waiting for this function to
         // return; if this function is slow then there may be some lag between capture and onNewData
         // for the next frame. If it's very slow then Royale may drop frames to catch up.
         // This sample code assumes that the UI toolkit will provide a callback to the paint() // method as needed, but does the initial processing of the data in the current thread.
         // This sample code uses option 3 above, the conversion from P DepthData to P MyFrameData is
         // done in this method, and MyFrameData provides all the data required for the paint()
         \ensuremath{//} method, without needing any pointers to the memory owned by the DepthData instance.
         // The image will also be scaled to the expected width, or may be scaled down to less than
         // the expected width if necessary for the height limitation.
         std::size_t scale = std::max ({size_t (lu), data->width / m_widthPerStream, data->height /
       MAX_HEIGHT } );
         std::size_t height = data->height / scale;
         // To reduce the depth data to ascii art, this sample discards most of the information in // the data. However, even if we had a full GUI, treating the depth data as an array of
         // (data->width * data->height) z coordinates would lose the accuracy. The 3D depth
         // points are not arranged in a rectilinear projection, and the discarded \boldsymbol{x} and \boldsymbol{y}
         // coordinates from the depth points account for the optical projection (or optical
         // distortion) of the camera.
         std::vector<std::string> asciiFrame;
         for (auto y = 0u; y < height; y++)
             std::string asciiLine;
             asciiLine.reserve (m_widthPerStream);
             for (auto x = 0u; x < m_widthPerStream; x++)
                  \ensuremath{//} There is a bounds-check in the asciiPoint function, it returns a space character
                  // if x or v is out-of-bounds.
                 asciiLine.push_back (asciiPoint (data, x * scale, y * scale));
             asciiFrame.push_back (std::move (asciiLine));
         // Scope for a lock while updating the internal model
```

Page: 154 of 173

API Documentation



```
std::unique_lock<std::mutex> lock (m_lockForReceivedData);
        auto &receivedData = m_receivedData[data->streamId];
        receivedData.asciiFrame.swap (asciiFrame);
        receivedData.exposureTimes = exposureTimes.toStdVector();
    ^{\prime\prime} // In a full application, the call below to paint() should be done in a separate thread, as
    // in a full application, the cash below to paint() should be done in a separate the common above. UI toolkits are expected to provide a method to // request an asynchronous repaint of the screen, without blocking onNewData().
    // But for the purposes of a demo, dropped frames are an accepted trade-off for not
    // depending on a specific UI toolkit.
    paint();
void paint ()
    // to show multiple streams side-by-size, we temporarily blit them in to this area
    std::vector<std::string> allFrames;
    std::map<royale::StreamId, std::vector<uint32_t» allExposureTimes;</pre>
    // scope for the thread-safety lock
        // while locked, copy the data to local structures
        std::unique_lock<std::mutex> lock (m_lockForReceivedData);
        if (m_receivedData.empty())
             return:
        // allocate the allFrames area, with a set of empty strings
             const auto received = m_receivedData.begin();
             allFrames.resize (received->second.asciiFrame.size());
             for (auto &str : allFrames)
                 str.reserve (m_width);
        // For each stream, append its data to each line of allFrames
        for (auto streamId : m_streamIds)
             const auto received = m_receivedData.find (streamId);
             if (received != m_receivedData.end())
                 for (auto y = Ou; y < allFrames.size(); y++)</pre>
                      // The at() in the next line could throw if streams have different-sized
                      // frames. That situation isn't expected in Royale, so this example omits
                      // error handling for this.
                      const auto &src = received->second.asciiFrame.at (y);
                      auto &dest = allFrames.at (y);
dest.append (src.begin(), src.end());
                 allExposureTimes[streamId] = received->second.exposureTimes;
             else
                 // There's no capture for this stream yet, leave a blank space
                 for (auto &dest : allFrames)
                      dest.append (m_widthPerStream, ' ');
    ^{\prime} // If this is a mixed mode (with multiple streams), print a header with the StreamIds
       (m_streamIds.size() > 1)
        for (auto streamId : m_streamIds)
             // streamIds are uint16_ts. To print them with C++'s '«' operator they should be
             // converted to unsigned, otherwise they may be interpreted as wide-characters.
```

Page: 155 of 173

API Documentation



```
cout « setw (static_cast<int> (m_widthPerStream)) « setfill (' ') « unsigned (streamId);
         // Print the data from all of the captured streams
         for (const auto &line : allFrames)
             cout « string (line.data(), line.size()) « endl;
         for (auto streamId : m_streamIds)
             const auto &exposureTimes = allExposureTimes.find (streamId);
             \verb|cout & "ExposureTimes for stream[" & static\_cast < unsigned > (streamId) & "] : "; \\
             if (exposureTimes == allExposureTimes.end())
                 cout « "no frames received yet for this stream";
             else
                 bool firstElementOfList = true;
                 for (const auto exposure : exposureTimes->second)
                      if (firstElementOfList)
                          firstElementOfList = false:
                      else
                          cout « ", ";
                      cout « exposure;
             cout « endl;
        }
    explicit MyListener (const royale::Vector<royale::StreamId> &streamIds) :
        m_width (MAX_WIDTH),
        m_widthPerStream (MAX_WIDTH / streamIds.size()),
        m streamIds (streamIds)
private:
    const std::size_t m_width;
    const std::size t m widthPerStream;
    const royale::Vector<royale::StreamId> m_streamIds;
    std::map<royale::StreamId, MyFrameData> m_receivedData;
    std::mutex m_lockForReceivedData;
int main (int argc, char **argv)
    // Windows requires that the application allocate these, not the DLL. We expect typical
    // Royale applications to be using a GUI toolkit such as Qt, which has its own equivalent of this
     // PlatformResources class (automatically set up by the toolkit).
    PlatformResources resources;
    // This is the data listener which will receive callbacks. It's declared
    // before the cameraDevice so that, if this function exits with a 'return' // statement while the camera is still capturing, it will still be in scope // until the cameraDevice's destructor implicitly deregisters the listener.
    unique_ptr<MyListener> listener;
    // this represents the main camera device object
    unique_ptr<royale::ICameraDevice> cameraDevice;
    // if non-null, load this file instead of connecting to a camera
unique_ptr<royale::String> rrfFile;
    // if non-null, choose this use case instead of the default
    unique_ptr<royale::String> commandLineUseCase;
         // Files recorded with RoyaleViewer have this filename extension
        const auto FILE_EXTENSION = royale::String (".rrf");
```

Page: 156 of 173

API Documentation



```
auto arg = std::unique_ptr<royale::String> (new royale::String (argv[1])); if (*arg == "--help" || *arg == "-h" || *arg == "/?" || argc > 2)
         cout « argv[0] « ":" « endl;
         cout « "--help, -h, /? : this help" « endl;
         cout « endl:
        cout « "With no command line arguments: opens a camera and retrieves data using the default use
   case" « endl;
        cout « endl;
         cout \ll "With an argument that ends \".rrf\": assumes the argument is the filename of a
   recording, and plays it \ddot{\text{\ }} « endl;
   cout \times "When playing back a recording, the only use case available is the one that was recorded." \times endl;
        cout « endl:
        cout « "With an argument that doesn't end \".rrf\": assumes the argument is the name of a
   use-case" « endl;
        cout \alpha "It will open the camera, and if there's a use case with that exact name will use it." \alpha
   endl;
        return 0;
    else if (arg->size() > FILE_EXTENSION.size() && 0 == arg->compare (arg->size() -
   FILE_EXTENSION.size(), FILE_EXTENSION.size(), FILE_EXTENSION))
         cout \mbox{\tt ``Assuming command-line argument is the filename of an RRF recording" <math>\mbox{\tt ``end};
         rrfFile = std::move (arg);
    else
    {
        cout « "Assuming command-line argument is the name of a use case, as it does not end \".rrf\"" «
   endl:
         commandLineUseCase = std::move (arg);
// the camera manager will either open a recording or query for a connected camera
if (rrfFile)
    royale::CameraManager manager;
    cameraDevice = manager.createCamera (*rrfFile);
else
    royale::CameraManager manager;
    auto camlist = manager.getConnectedCameraList();
cout « "Detected " « camlist.size() « " camera(s)." « endl;
    if (!camlist.empty())
    {
         cout « "CamID for first device: " « camlist.at (0).c_str() « " with a length of (" « camlist.at
   (0).length() « ")" « endl;
       cameraDevice = manager.createCamera (camlist[0]);
// the camera device is now available and CameraManager can be deallocated here
if (cameraDevice == nullptr)
    cerr « "Cannot create the camera device" « endl;
    return 1;
// IMPORTANT: call the initialize method before working with the camera device
if (cameraDevice->initialize() != royale::CameraStatus::SUCCESS)
    cerr « "Cannot initialize the camera device" « endl;
    return 1;
royale::Vector<royale::String> useCases;
auto status = cameraDevice->getUseCases (useCases);
if (status != royale::CameraStatus::SUCCESS || useCases.empty())
    cerr « "No use cases are available" « endl;
cerr « "getUseCases() returned: " « getErrorString (status) « endl;
    return 1;
```

Page: 157 of 173

API Documentation



```
// choose a use case
auto selectedUseCaseIdx = 0u;
if (commandLineUseCase)
    auto useCaseFound = false;
for (auto i = 0u; i < useCases.size(); ++i)</pre>
        if (*commandLineUseCase == useCases[i])
        {
             selectedUseCaseIdx = i;
             useCaseFound = true;
             break;
    if (!useCaseFound)
        cerr « "Error: the chosen use case is not supported by this camera" « endl;
        \verb|cerr "A list of supported use cases is printed by sampleCameraInfo" " endl; \\
        return 1:
}
else
   // choose the first use case
selectedUseCaseIdx = 0;
// set an operation mode
if (cameraDevice->setUseCase (useCases.at (selectedUseCaseIdx)) != royale::CameraStatus::SUCCESS)
    cerr « "Error setting use case" « endl;
    return 1;
^{\prime} // Retrieve the IDs of the different streams
royale::Vector<royale::StreamId> streamIds;
  (cameraDevice->getStreams (streamIds) != royale::CameraStatus::SUCCESS)
    cerr « "Error retrieving streams" « endl;
    return 1:
cout « "Stream IDs : ";
for (auto curStream : streamIds)
    cout « curStream « ", ";
cout « endl;
// register a data listener
listener.reset (new MyListener (streamIds));
if (cameraDevice->registerDataListener (listener.get()) != royale::CameraStatus::SUCCESS)
   cerr « "Error registering data listener" « endl;
   return 1;
if (cameraDevice->startCapture() != royale::CameraStatus::SUCCESS)
    cerr \ll "Error starting the capturing" \ll endl;
    return 1:
^{\prime}// let the camera capture for some time
this_thread::sleep_for (chrono::seconds (5));
// Change the exposure time for the first stream of the use case (Royale will limit this to an // eye-safe exposure time, with limits defined by the use case). The time is given in
// microseconds.
// Non-mixed mode use cases have exactly one stream, mixed mode use cases have more than one.
// For this example we only change the first stream.
if (cameraDevice->setExposureTime (200, streamIds[0]) != royale::CameraStatus::SUCCESS)
    cerr « "Cannot set exposure time for stream" « streamIds[0] « endl;
```

Page: 158 of 173

API Documentation



```
else
{
    cout « "Changed exposure time for stream " « streamIds[0] « " to 200 microseconds ..." « endl;
}
// let the camera capture for some time
this_thread::sleep_for (chrono::seconds (5));
// stop capture mode
if (cameraDevice->stopCapture() != royale::CameraStatus::SUCCESS)
{
    cerr « "Error stopping the capturing" « endl;
    return 1;
}
return 0;
```

Page: 159 of 173

API Documentation



Page: 160 of 173

API Documentation



Index

\sim CameraManager	royale, 26
CameraManager, 30	AF1
\sim ICameraDevice	royale, 23
ICameraDevice, 47	amplitude
\sim IDepthDataListener	IntermediatePoint, 90
IDepthDataListener, 73	AUTO
~IDepthIRImageListener	royale, 26
IDepthIRImageListener, 75	AutoExpoMax_Int
~IDepthImageListener	royale, 25
IDepthImageListener, 74	AutoExpoMin_Int
~IEvent	royale, 25
IEvent, 76	AutoExposureRefAmplitude_Float
\sim IEventListener	royale, 24
IEventListener, 78	AutoExposureRefValue_Float
\sim IExposureListener	royale, 24
IExposureListener, 79	AUTOMATIC
~IExposureListener2	royale, 22
IExposureListener2, 81	•
~IExtendedData	b
IExtendedData, 82	Variant, 118
\sim IExtendedDataListener	Binning_10_Basic
IExtendedDataListener, 84	royale, 23
~IIRImageListener	Binning_10_Efficiency
IIRImageListener, 85	royale, 23
~IPlaybackStopListener	Binning_1_Basic
IPlaybackStopListener, 91	royale, 23
∼IRecord	Binning_1_Efficiency
IRecord, 93	royale, 23
~IRecordStopListener	Binning_2_Basic
IRecordStopListener, 96	royale, 23
~IReplay	Binning_2_Efficiency
IReplay, 98	royale, 23
~ISparsePointCloudListener	Binning_3_Basic
ISparsePointCloudListener, 104	royale, 23
~Variant	Binning_3_Efficiency
Variant, 115	royale, 23
·	Binning_4_Basic
AdaptiveNoiseFilterType_Int	royale, 23
royale, 24	Binning 4 Efficiency
ADD_DEBUG_CONSOLE	royale, 23
Definitions.hpp, 122	Binning_8_Basic
AF	royale, 23

Page: 161 of 173

API Documentation



```
Binning_8_Efficiency
                                                                  IRImage, 102
     royale, 23
                                                            DATA_NOT_FOUND
Bool
                                                                  royale, 20
     royale, 26
                                                            Definitions.hpp, 122
                                                                  ADD_DEBUG_CONSOLE, 122
CALIBRATION_DATA_ERROR
                                                                  ROYALE_API, 122
     royale, 21
                                                            Deprecated1
CallbackData
                                                                  royale, 23
     royale, 19
                                                             Deprecated2
CallbackData.hpp, 121
                                                                  royale, 23
CameraAccessLevel
                                                             Deprecated3
     royale, 20
                                                                  royale, 23
CameraAccessLevel.hpp, 121
                                                            Deprecated4
CameraManager, 29
                                                                  royale, 23
     \simCameraManager, 30
                                                            Depth
     CameraManager, 30
                                                                  royale, 19
     createCamera, 30
                                                            depthConfidence
     getAccessLevel, 31
                                                                  DepthPoint, 42
     getConnectedCameraList, 31
                                                            DepthData, 34
     getConnectedCameraNames, 32
                                                                  exposureTimes, 36
     registerEventListener, 32
                                                                  hasDepth, 36
     setCacheFolder, 33
                                                                  height, 36
     unregisterEventListener, 33
                                                                  operator=, 35
CameraManager.hpp, 122
                                                                  points, 36
CameraStatus
                                                                  streamld, 36
     royale, 20
                                                                  timeStamp, 37
CB_BINNED_NG
                                                                  version. 37
     royale, 26
                                                                  width. 37
CB BINNED WS
                                                            DepthData.hpp, 123
     royale, 26
                                                            DepthImage, 38
CCThresh_Int
                                                                  cdData, 38
     royale, 25
                                                                  height, 38
cdData
                                                                  streamld, 39
     DepthImage, 38
                                                                  timestamp, 39
CM1
                                                                  width, 39
     royale, 23
                                                            DepthImage.hpp, 123
CM FI
                                                             DepthIRImage, 39
     royale, 26
                                                                  dpData, 40
combineProcessingMaps
                                                                  height, 40
     royale, 26
                                                                  irData, 40
ConsistencyTolerance_Float
                                                                  streamld, 41
     royale, 24
                                                                  timestamp, 41
COULD_NOT_OPEN
                                                                  width, 41
     royale, 20
                                                            DepthIRImage.hpp, 124
createCamera
                                                            DepthPoint, 41
     CameraManager, 30
                                                                  depthConfidence, 42
currentFrame
     IReplay, 98
                                                                  grayValue, 42
Custom
                                                                  noise, 42
     royale, 23
                                                                  x, 43
                                                                  y, <mark>43</mark>
data
                                                                  z, <mark>43</mark>
```

Page: 162 of 173

API Documentation



describe	FlyingPixelAmpThreshold_Float
IEvent, 76	royale, 25
DEVICE_ALREADY_INITIALIZED	FlyingPixelAngleLimit_Float
royale, 21	royale, 25
DEVICE_IS_BUSY	FlyingPixelMaxNeighbors_Int
royale, 20	royale, 25
DEVICE_NOT_INITIALIZED	FlyingPixelMinNeighbors_Int
royale, 21	royale, 25
DISCONNECTED	FlyingPixelNoiseRatioThresh_Float
royale, 20	royale, 25
distance	FlyingPixelsF0_Float
IntermediatePoint, 90	royale, 24
distortionRadial	FlyingPixelsF1_Float
LensParameters, 105	royale, 24
distortionTangential	FlyingPixelsFarDist_Float
LensParameters, 105	royale, 24
dpData	FlyingPixelsNearDist_Float
DepthIRImage, 40	royale, 24
DUTYCYCLE_NOT_SUPPORTED	focalLength
royale, 21	LensParameters, 106
•	frameCount
Enum	IReplay, 98
royale, 26	FRAMERATE_NOT_SUPPORTED
EventSeverity	royale, 21
royale, 21	FSM_INVALID_TRANSITION
EventType	royale, 21
royale, 21	Full
EXPOSURE_MODE_INVALID	royale, 23
royale, 21	•
EXPOSURE_TIME_NOT_SUPPORTED	getAccessLevel
royale, 21	CameraManager, 31
exposureGroupNames	ICameraDevice, 47
RawData, 108	getBool
ExposureMode	Variant, 115
royale, 22	getBuildVersion
ExposureMode.hpp, 124	IReplay, 98
exposureTimes	getCalibrationData
DepthData, 36	ICameraDevice, 47
IntermediateData, 87	getCameraInfo
RawData, 108	ICameraDevice, 48
	getCameraName
f	ICameraDevice, 48
Variant, 119	getConnectedCameraList
FILE_NOT_FOUND	CameraManager, 31
royale, 20	getConnectedCameraNames
FilterLevel	CameraManager, 32
royale, 23	getCurrentUseCase
FilterLevel.hpp, 124	ICameraDevice, 48
flags	getData
IntermediatePoint, 90	Variant, 115
Float	getDepthData
royale, 26	IExtendedData, 82
-	•

Page: 163 of 173

API Documentation



```
getEnumString
                                                                 IReplay, 99
     Variant, 115
                                                            getNumberOfStreams
getEnumValue
                                                                 ICameraDevice, 52
     Variant, 115
                                                            getPatchVersion
getExposureGroups
                                                                 IReplay, 99
                                                            getPlaybackRange
     ICameraDevice, 49
                                                                 IReplay, 99
getExposureLimits
                                                            getPossibleVals
     ICameraDevice, 49
                                                                 Variant, 116
getExposureMode
                                                            getProcessingFlagName
     ICameraDevice, 50
                                                                 royale, 27
getFileVersion
                                                            getProcessingParameters
     IReplay, 98
                                                                 ICameraDevice, 54
getFilterLevel
                                                            getRawData
     ICameraDevice, 50
                                                                 IExtendedData, 83
getFilterLevelFromName
                                                            getSpectreProcessingTypeFromName
     royale, 27
                                                                 royale, 27
getFilterLevelName
                                                            getSpectreProcessingTypeName
    royale, 27
                                                                 royale, 27
getFilterLevels
                                                            getStatusString
     ICameraDevice, 50
                                                                 royale, 28
getFloat
                                                            getStreams
     Variant, 115
                                                                 ICameraDevice, 54
getFloatMax
                                                            getUseCases
     Variant, 116
                                                                 ICameraDevice, 54
getFloatMin
                                                            GlobalBinning_Int
     Variant, 116
                                                                 royale, 24
getFrameRate
                                                            GRAY_IMAGE
     ICameraDevice, 50
                                                                 royale, 26
getld
                                                            GrayImageMeanMap_Int
     ICameraDevice, 51
                                                                 royale, 25
getInt
                                                            grayValue
     Variant, 116
                                                                 DepthPoint, 42
getIntermediateData
     IExtendedData, 82
                                                            hasDepth
getIntMax
                                                                 DepthData, 36
     Variant, 116
                                                            hasDepthData
getIntMin
                                                                 IExtendedData, 83
     Variant, 116
                                                            hasIntermediateData
getLensCenter
                                                                 IExtendedData, 83
     ICameraDevice, 51
                                                            hasRawData
getLensParameters
                                                                 IExtendedData, 83
     ICameraDevice, 52
                                                            height
getMajorVersion
                                                                 DepthData, 36
     IReplay, 99
                                                                 DepthImage, 38
getMaxFrameRate
                                                                 DepthIRImage, 40
     ICameraDevice, 52
                                                                 IntermediateData, 87
getMaxSensorHeight
                                                                 IRImage, 102
     ICameraDevice, 52
                                                                 RawData, 108
getMaxSensorWidth
     ICameraDevice, 52
                                                           i
getMinorVersion
                                                                 Variant, 119
```

Page: 164 of 173

API Documentation



```
ICameraDevice, 43
                                                                  startCapture, 67
     ~ICameraDevice, 47
                                                                  startRecording, 67
     getAccessLevel, 47
                                                                  stopCapture, 68
     getCalibrationData, 47
                                                                  stopRecording, 68
     getCameraInfo, 48
                                                                  unregisterDataListener, 68
     getCameraName, 48
                                                                  unregisterDataListenerExtended, 69
     getCurrentUseCase, 48
                                                                  unregisterDepthImageListener, 69
     getExposureGroups, 49
                                                                  unregisterDepthIRImageListener, 69
     getExposureLimits, 49
                                                                  unregisterEventListener, 69
     getExposureMode, 50
                                                                  unregisterExposureListener, 69
     getFilterLevel, 50
                                                                  unregisterIRImageListener, 70
     getFilterLevels, 50
                                                                  unregisterRecordListener, 70
     getFrameRate, 50
                                                                  unregisterSparsePointCloudListener, 70
     getld, 51
                                                                  writeCalibrationToFlash, 70
     getLensCenter, 51
                                                                  writeDataToFlash, 70, 71
     getLensParameters, 52
                                                                  writeRegisters, 71
     getMaxFrameRate, 52
                                                             ICameraDevice.hpp, 125
     getMaxSensorHeight, 52
                                                             IDepthDataListener, 72
     getMaxSensorWidth, 52
                                                                   ~IDepthDataListener, 73
     getNumberOfStreams, 52
                                                                  onNewData, 73
     getProcessingParameters, 54
                                                             IDepthDataListener.hpp, 126
                                                             IDepthImageListener, 73
     getStreams, 54
     getUseCases, 54
                                                                   ~IDepthImageListener, 74
                                                                  onNewData, 74
     initialize, 54, 55
     isCalibrated, 55
                                                             IDepthImageListener.hpp, 126
     isCapturing, 56
                                                             IDepthIRImageListener, 74
     isConnected, 56
                                                                   ~IDepthIRImageListener, 75
     readRegisters, 56
                                                                  onNewData, 75
                                                             IDepthIRImageListener.hpp, 127
     registerDataListener, 57
     registerDataListenerExtended, 57
                                                             IEvent. 76
     registerDepthImageListener, 58
                                                                  \simIEvent, 76
     registerDepthIRImageListener, 58
                                                                  describe, 76
     registerEventListener, 58
                                                                  severity, 77
     registerExposureListener, 59
                                                                  type, 77
     registerIRImageListener, 59
                                                             IEvent.hpp, 127
     registerRecordListener, 60
                                                             IEventListener, 78
     registerSparsePointCloudListener, 60
                                                                  ~IEventListener, 78
     setCalibrationData, 60, 61
                                                                  onEvent, 78
     setCallbackData, 61
                                                             IEventListener.hpp, 128
     setDutyCycle, 62
                                                             IExposureListener, 79
     setExposureForGroups, 62
                                                                   ~IExposureListener, 79
     setExposureMode, 63
                                                                  onNewExposure, 80
     setExposureTime, 63, 64
                                                             IExposureListener.hpp, 128
     setExposureTimes, 64
                                                             IExposureListener2, 80
     setExternalTrigger, 65
                                                                   ~IExposureListener2, 81
     setFilterLevel, 65
                                                                  onNewExposure, 81
     setFrameRate, 65
                                                             IExposureListener2.hpp, 128
     setProcessingParameters, 65
                                                             IExtendedData, 81
                                                                   ~IExtendedData, 82
     setProcessingThreads, 66
                                                                  getDepthData, 82
     setUseCase, 66
     shiftLensCenter, 67
                                                                  getIntermediateData, 82
```

Page: 165 of 173

API Documentation



```
getRawData, 83
                                                                   onPlaybackStopped, 92
     hasDepthData, 83
                                                             IPlaybackStopListener.hpp, 131
     hasIntermediateData, 83
     hasRawData, 83
                                                                   royale, 23
IExtendedData.hpp, 129
                                                             IR2
IExtendedDataListener, 84
                                                                   royale, 23
     ~IExtendedDataListener, 84
                                                             irData
     onNewData, 84
                                                                   DepthIRImage, 40
IExtendedDataListener.hpp, 129
                                                             IRecord, 92
                                                                   ∼IRecord, 93
IIRImageListener, 85
     ~IIRImageListener, 85
                                                                   isRecording, 93
     onNewData, 85
                                                                   operator bool, 93
IIRImageListener.hpp, 130
                                                                   registerEventListener, 93
illuminationEnabled
                                                                   resetParameters, 94
                                                                   setFrameCaptureListener, 94
     RawData, 108
                                                                   setProcessingParameters, 94
illuminationTemperature
     RawData, 109
                                                                   startRecord, 94
                                                                   stopRecord, 95
initialize
                                                                   unregisterEventListener, 95
     ICameraDevice, 54, 55
INSUFFICIENT_BANDWIDTH
                                                             IRecord.hpp, 131
                                                             IRecordStopListener, 95
     royale, 21
INSUFFICIENT_PRIVILEGES
                                                                   \simIRecordStopListener, 96
                                                                   onRecordingStopped, 96
     royale, 21
                                                             IRecordStopListener.hpp, 131
Int
                                                             IReplay, 97
     royale, 26
                                                                   \simIReplay, 98
intensity
     IntermediatePoint, 90
                                                                   currentFrame, 98
Intermediate
                                                                   frameCount. 98
     royale, 19
                                                                   getBuildVersion, 98
IntermediateData, 86
                                                                   getFileVersion, 98
     exposureTimes, 87
                                                                   getMajorVersion, 99
                                                                   getMinorVersion, 99
     height, 87
                                                                   getPatchVersion, 99
     modulationFrequencies, 87
     numFrequencies, 87
                                                                   getPlaybackRange, 99
                                                                   loop, 99
     operator=, 87
     points, 88
                                                                   pause, 100
     processingParameters, 88
                                                                   registerStopListener, 100
     streamld, 88
                                                                   resume, 100
     timeStamp, 88
                                                                   seek, 100
     version, 88
                                                                   setPlaybackRange, 101
     width, 89
                                                                   unregisterStopListener, 101
IntermediateData.hpp, 130
                                                                   useTimestamps, 101
IntermediatePoint, 89
                                                             IReplay.hpp, 132
     amplitude, 90
                                                             IRImage, 102
     distance, 90
                                                                   data, 102
     flags, 90
                                                                   height, 102
     intensity, 90
                                                                   streamld, 103
INVALID_VALUE
                                                                   timestamp, 103
     royale, 20
                                                                   width, 103
IPlaybackStopListener, 91
                                                             IRImage.hpp, 132
     ~IPlaybackStopListener, 91
                                                             isCalibrated
```

Page: 166 of 173

API Documentation



10 0 1 5	
ICameraDevice, 55	royale, 21
isCapturing	NO_USE_CASES
ICameraDevice, 56	royale, 21
isConnected	NO_USE_CASES_FOR_LEVEL
ICameraDevice, 56	royale, 21
ISparsePointCloudListener, 103	noise
~ISparsePointCloudListener, 104	DepthPoint, 42
onNewData, 104	NoiseFilterIterations_Int
ISparsePointCloudListener.hpp, 133	royale, 25
isRecording	NoiseFilterSigmaA_Float
IRecord, 93	royale, 25
14	NoiseFilterSigmaD_Float
L1	royale, 25
royale, 20	NoiseThreshold_Float
L2	royale, 24
royale, 20	None
L3	royale, 19
royale, 20	NOT_IMPLEMENTED
L4	royale, 20
royale, 20	NUM_FLAGS
Legacy	royale, 25
royale, 23	NUM_TYPES
LensParameters, 105	royale, 26
distortionRadial, 105	numFrequencies
distortionTangential, 105	IntermediateData, 87
focalLength, 106	numPoints
principalPoint, 106	SparsePointCloud, 111
LensParameters.hpp, 133	Off
LOGIC_ERROR	royale, 23
royale, 20	onEvent
loop	IEventListener, 78
IReplay, 99	onNewData
LowerSaturationThreshold_Int	IDepthDataListener, 73
royale, 24	IDepthImageListener, 74
MANILIAI	IDepthIRImageListener, 75
MANUAL TOURIS 22	IExtendedDataListener, 84
royale, 22	IIRImageListener, 85
MASTER	ISparsePointCloudListener, 104
royale, 26	•
modulationFrequencies	onNewExposure IExposureListener, 80
IntermediateData, 87	IExposureListener, 80
RawData, 109	onPlaybackStopped
MPIAmpThreshold_Float	IPlaybackStopListener, 92
royale, 24	onRecordingStopped
MPIDistThreshold_Float	IRecordStopListener, 96
royale, 24	operator bool
MPINoiseDistance_Float	IRecord, 93
royale, 24	operator!=
NG	
royale, 26	Variant, 117 operator<
NO_CALIBRATION_DATA	Variant, 117
	variant, 117

Page: 167 of 173

API Documentation



```
operator<<
                                                                 RawData, 109
     royale, 28
                                                            RawData.hpp, 135
operator=
                                                            rawFrameCount
     DepthData, 35
                                                                 RawData, 109
     IntermediateData, 87
                                                            README.md, 135
operator==
                                                            readRegisters
     Variant, 117
                                                                 ICameraDevice, 56
OUT_OF_BOUNDS
                                                            registerDataListener
     royale, 20
                                                                 ICameraDevice, 57
                                                            registerDataListenerExtended
parseProcessingFlagName
                                                                 ICameraDevice, 57
     royale, 28
                                                            registerDepthImageListener
pause
                                                                 ICameraDevice, 58
     IReplay, 100
                                                            registerDepthIRImageListener
phaseAngles
                                                                 ICameraDevice, 58
     RawData, 109
                                                            registerEventListener
PhaseNoiseThresh_Float
                                                                 CameraManager, 32
     royale, 25
                                                                 ICameraDevice, 58
points
                                                                 IRecord, 93
     DepthData, 36
                                                            registerExposureListener
     IntermediateData, 88
                                                                 ICameraDevice, 59
principalPoint
                                                            registerIRImageListener
     LensParameters, 106
                                                                 ICameraDevice, 59
ProcessingFlag
                                                            registerRecordListener
     royale, 23
                                                                 ICameraDevice, 60
ProcessingFlag.hpp, 134
                                                            registerSparsePointCloudListener
ProcessingParameterMap
                                                                 ICameraDevice, 60
     royale, 18
                                                            registerStopListener
ProcessingParameterPair
                                                                 IReplay, 100
     royale, 18
                                                            Reserved1
processingParameters
                                                                 royale, 25
     IntermediateData, 88
                                                            Reserved2
ProcessingParameterVector
                                                                 royale, 25
     royale, 18
                                                            Reserved3
                                                                 royale, 25
Raw
                                                            Reserved4
     royale, 19
                                                                 royale, 25
RawData, 106
                                                            Reserved5
     exposureGroupNames, 108
                                                                 royale, 25
     exposureTimes, 108
                                                            Reserved6
     height, 108
                                                                 royale, 25
     illuminationEnabled, 108
                                                            Reserved7
     illuminationTemperature, 109
                                                                 royale, 25
     modulationFrequencies, 109
     phaseAngles, 109
                                                            Reserved8
     RawData, 107, 108
                                                                 royale, 25
     rawData, 109
                                                            resetParameters
     rawFrameCount, 109
                                                                 IRecord, 94
     streamld, 110
                                                            RESOURCE_ERROR
     timeStamp, 110
                                                                 royale, 20
     width, 110
                                                            resume
rawData
                                                                 IReplay, 100
```

Page: 168 of 173

API Documentation



Royale, 13	EXPOSURE_MODE_INVALID, 21
royale, 15	EXPOSURE_TIME_NOT_SUPPORTED, 21
AdaptiveNoiseFilterType_Int, 24	ExposureMode, 22
AF, 26	FILE_NOT_FOUND, 20
AF1, 23	FilterLevel, 23
AUTO, 26	Float, 26
AutoExpoMax_Int, 25	FlyingPixelAmpThreshold_Float, 25
AutoExpoMin_Int, 25	FlyingPixelAngleLimit_Float, 25
AutoExposureRefAmplitude_Float, 24	FlyingPixelMaxNeighbors Int, 25
AutoExposureRefValue_Float, 24	FlyingPixelMinNeighbors_Int, 25
AUTOMATIC, 22	FlyingPixelNoiseRatioThresh_Float, 25
Binning_10_Basic, 23	FlyingPixelsF0 Float, 24
Binning_10_Efficiency, 23	FlyingPixelsF1_Float, 24
Binning_1_Basic, 23	FlyingPixelsFarDist_Float, 24
Binning_1_Efficiency, 23	FlyingPixelsNearDist_Float, 24
Binning_2_Basic, 23	FRAMERATE_NOT_SUPPORTED, 21
Binning_2_Efficiency, 23	FSM_INVALID_TRANSITION, 21
Binning_3_Basic, 23	Full, 23
Binning_3_Efficiency, 23	getFilterLevelFromName, 27
Binning_4_Basic, 23	getFilterLevelName, 27
Binning 4 Efficiency, 23	getProcessingFlagName, 27
Binning 8 Basic, 23	getSpectreProcessingTypeFromName, 27
Binning_8_Efficiency, 23	getSpectreProcessingTypeName, 27
Bool, 26	getStatusString, 28
CALIBRATION_DATA_ERROR, 21	GlobalBinning_Int, 24
CallbackData, 19	GRAY IMAGE, 26
CameraAccessLevel, 20	GrayImageMeanMap_Int, 25
CameraStatus, 20	INSUFFICIENT_BANDWIDTH, 21
CB_BINNED_NG, 26	INSUFFICIENT_PRIVILEGES, 21
CB_BINNED_WS, 26	Int, 26
CCThresh_Int, 25	Intermediate, 19
CM1, 23	INVALID_VALUE, 20
CM_FI, 26	IR1, 23
combineProcessingMaps, 26	IR2, 23
ConsistencyTolerance_Float, 24	L1, 20
COULD_NOT_OPEN, 20	L2, 20
Custom, 23	L3, 20
DATA_NOT_FOUND, 20	L4, 20
Deprecated1, 23	Legacy, 23
Deprecated2, 23	LOGIC_ERROR, 20
Deprecated3, 23	LowerSaturationThreshold_Int, 24
Deprecated4, 23	MANUAL, 22
Depth, 19	MASTER, 26
DEVICE_ALREADY_INITIALIZED, 21	MPIAmpThreshold_Float, 24
DEVICE_IS_BUSY, 20	MPIDistThreshold_Float, 24
DEVICE_NOT_INITIALIZED, 21	MPINoiseDistance_Float, 24
DISCONNECTED, 20	NG, 26
DUTYCYCLE_NOT_SUPPORTED, 21	NO_CALIBRATION_DATA, 21
Enum, 26	NO_USE_CASES, 21
EventSeverity, 21	NO_USE_CASES_FOR_LEVEL, 21
EventType, 21	NoiseFilterIterations_Int, 25

Page: 169 of 173

API Documentation



NoiseFilterSigmaA_Float, 25	TIMEOUT, 20
NoiseFilterSigmaD_Float, 25	TriggerMode, 26
NoiseThreshold_Float, 24	TwoFreqCombinationType_Int, 25
None, 19	UNKNOWN, 21
NOT_IMPLEMENTED, 20	UpperSaturationThreshold_Int, 24
NUM_FLAGS, 25	UseAdaptiveBinning_Bool, 24
NUM_TYPES, 26	UseAdaptiveNoiseFilter_Bool, 24
Off, 23	UseAutoExposure_Bool, 24
operator<<, 28	USECASE_NOT_SUPPORTED, 20
OUT_OF_BOUNDS, 20	UseCorrectMPI_Bool, 25
parseProcessingFlagName, 28	UseFilter2Freq_Bool, 24
PhaseNoiseThresh_Float, 25	UseFlagSBI_Bool, 25
ProcessingFlag, 23	UseGrayImageFallbackAmplitude_Bool, 25
ProcessingParameterMap, 18	UseHoleFilling_Bool, 25
ProcessingParameterPair, 18	UseMPIFlag_Amp_Bool, 24
ProcessingParameterVector, 18	UseMPIFlag_Dist_Bool, 24
Raw, 19	UseMPIFlagAverage_Bool, 24
Reserved1, 25	UseRemoveFlyingPixel_Bool, 24
Reserved2, 25	UseRemoveStrayLight_Bool, 24
Reserved3, 25	UseSmoothingFilter_Bool, 24
Reserved4, 25	UseSparsePointCloud_Bool, 24
Reserved5, 25	UseValidateImage_Bool, 24
Reserved6, 25	VariantType, 26
Reserved7, 25	WRONG_DATA_FORMAT_FOUND, 20
Reserved8, 25	royale::parameter, 28
RESOURCE ERROR, 20	ROYALE API
ROYALE_CAPTURE_STREAM, 22	Definitions.hpp, 122
ROYALE_DEVICE_DISCONNECTED, 22	ROYALE_CAPTURE_STREAM
ROYALE ERROR, 21	royale, 22
ROYALE ERROR DESCRIPTION, 22	ROYALE_DEVICE_DISCONNECTED
ROYALE_EYE_SAFETY, 22	royale, 22
ROYALE FATAL, 21	ROYALE ERROR
ROYALE FRAME DROP, 22	royale, 21
ROYALE_INFO, 21	ROYALE_ERROR_DESCRIPTION
ROYALE_OVER_TEMPERATURE, 22	royale, 22
ROYALE PROCESSING, 22	ROYALE EYE SAFETY
ROYALE_RAW_FRAME_STATS, 22	royale, 22
ROYALE_RECORDING, 22	ROYALE_FATAL
ROYALE_UNKNOWN, 22	royale, 21
ROYALE_WARNING, 21	ROYALE_FRAME_DROP
RUNTIME_ERROR, 20	royale, 22
SLAVE, 26	ROYALE_INFO
SmoothingAlpha_Float, 24	royale, 21
SmoothingFilterResetThreshold_Float, 25	ROYALE_OVER_TEMPERATURE
SmoothingFilterType_Int, 24	royale, 22
SPECTRE_NOT_INITIALIZED, 21	ROYALE_PROCESSING
Spectre_Not_intrialized, 21 SpectreProcessingType, 25	royale, 22
SpectreProcessingType_Int, 25	•
• • • •	ROYALE_RAW_FRAME_STATS
StraylightThreshold_Float, 25 StreamId, 19	royale, 22
•	ROYALE_RECORDING
SUCCESS, 20	royale, 22

Page: 170 of 173

API Documentation



ROYALE_UNKNOWN	severity
royale, 22	IEvent, 77
ROYALE_WARNING	shiftLensCenter
royale, 21	ICameraDevice, 67
RUNTIME_ERROR	SLAVE
royale, 20	royale, 26
	SmoothingAlpha_Float
seek	royale, 24
IReplay, 100	SmoothingFilterResetThreshold_Floa
setBool	royale, 25
Variant, 117	SmoothingFilterType_Int
setCacheFolder	royale, 24
CameraManager, 33	SparsePointCloud, 110
setCalibrationData	•
ICameraDevice, 60, 61	numPoints, 111
setCallbackData	streamld, 111
ICameraDevice, 61	timestamp, 111
setData	xyzcPoints, 112
Variant, 117	SparsePointCloud.hpp, 135
setDutyCycle	SPECTRE_NOT_INITIALIZED
ICameraDevice, 62	royale, 21
setEnumValue	SpectreProcessingType
Variant, 117, 118	royale, 25
setExposureForGroups	SpectreProcessingType.hpp, 136
ICameraDevice, 62	SpectreProcessingType_Int
•	royale, <mark>25</mark>
setExposureMode	startCapture
ICameraDevice, 63	ICameraDevice, 67
setExposureTime	startRecord
ICameraDevice, 63, 64	IRecord, 94
setExposureTimes	startRecording
ICameraDevice, 64	ICameraDevice, 67
setExternalTrigger	Status.hpp, 136
ICameraDevice, 65	stopCapture
setFilterLevel	ICameraDevice, 68
ICameraDevice, 65	stopRecord
setFloat	·
Variant, 118	IRecord, 95
setFrameCaptureListener	stopRecording
IRecord, 94	ICameraDevice, 68
setFrameRate	StraylightThreshold_Float
ICameraDevice, 65	royale, 25
setInt	StreamId
Variant, 118	royale, 19
setPlaybackRange	streamld
IReplay, 101	DepthData, 36
setProcessingParameters	DepthImage, 39
ICameraDevice, 65	DepthIRImage, 41
IRecord, 94	IntermediateData, 88
setProcessingThreads	IRImage, 103
ICameraDevice, 66	RawData, 110
setUseCase	SparsePointCloud, 111
ICameraDevice, 66	Streamld.hpp, 137
ioaniorabovico, oo	οιισαιπιστήρη, τον

Page: 171 of 173

API Documentation



SUCCESS	UseAutoExposure_Bool
royale, 20	royale, 24
	USECASE_NOT_SUPPORTED
TIMEOUT	royale, 20
royale, 20	UseCorrectMPI Bool
timeStamp	royale, 25
DepthData, 37	UseFilter2Freq_Bool
IntermediateData, 88	royale, 24
RawData, 110	UseFlagSBI_Bool
timestamp	royale, 25
DepthImage, 39	UseGrayImageFallbackAmplitude_Bool
DepthIRImage, 41	royale, 25
IRImage, 103	UseHoleFilling_Bool
SparsePointCloud, 111	royale, 25
TriggerMode	UseMPIFlag_Amp_Bool
royale, 26	royale, 24
TriggerMode.hpp, 138	
TwoFreqCombinationType_Int	UseMPIFlag_Dist_Bool
royale, 25	royale, 24
	UseMPIFlagAverage_Bool
type	royale, 24
IEvent, 77	UseRemoveFlyingPixel_Bool
UNKNOWN	royale, 24
royale, 21	UseRemoveStrayLight_Bool
	royale, 24
unregisterDataListener ICameraDevice, 68	UseSmoothingFilter_Bool
•	royale, 24
unregisterDataListenerExtended	UseSparsePointCloud_Bool
ICameraDevice, 69	royale, 24
unregisterDepthImageListener	useTimestamps
ICameraDevice, 69	IReplay, 101
unregisterDepthIRImageListener	UseValidateImage_Bool
ICameraDevice, 69	royale, 24
unregisterEventListener	Variant 110
CameraManager, 33	Variant, 112
ICameraDevice, 69	~Variant, 115
IRecord, 95	b, 118
unregisterExposureListener	f, 119
ICameraDevice, 69	getBool, 115
unregisterIRImageListener	getData, 115
ICameraDevice, 70	getEnumString, 115
unregisterRecordListener	getEnumValue, 115
ICameraDevice, 70	getFloat, 115
unregisterSparsePointCloudListener	getFloatMax, 116
ICameraDevice, 70	getFloatMin, 116
unregisterStopListener	getInt, 116
IReplay, 101	getIntMax, 116
UpperSaturationThreshold_Int	getIntMin, 116
royale, 24	getPossibleVals, 116
UseAdaptiveBinning_Bool	i, 119
royale, 24	operator!=, 117
UseAdaptiveNoiseFilter_Bool	operator<, 117
royale, 24	operator==, 117

Page: 172 of 173

API Documentation



```
setBool, 117
     setData, 117
     setEnumValue, 117, 118
     setFloat, 118
     setInt, 118
     Variant, 113, 114
     variantType, 118
Variant.hpp, 138
Variant::InvalidType, 91
VariantType
     royale, 26
variantType
     Variant, 118
version
     DepthData, 37
     IntermediateData, 88
width
     DepthData, 37
     DepthImage, 39
     DepthIRImage, 41
     IntermediateData, 89
     IRImage, 103
     RawData, 110
write Calibration To Flash \\
     ICameraDevice, 70
writeDataToFlash
     ICameraDevice, 70, 71
writeRegisters
     ICameraDevice, 71
WRONG_DATA_FORMAT_FOUND
     royale, 20
     DepthPoint, 43
xyzcPoints
     SparsePointCloud, 112
У
     DepthPoint, 43
```

DepthPoint, 43

Page: 173 of 173